

# Imperx Camera SDK

## 1.5.0.54

Generated by Doxygen 1.8.13



# Contents

<b>1</b>	<b>Imperx Camera C++ SDK</b>	<b>1</b>
1.1	General Information . . . . .	1
1.2	lpxCameraApi library . . . . .	1
1.2.1	lpxCam namespace . . . . .	1
1.2.2	lpxGenParam namespace . . . . .	2
1.3	lpxCameraGuiApi library . . . . .	2
<b>2</b>	<b>Deprecated List</b>	<b>3</b>
<b>3</b>	<b>Namespace Index</b>	<b>5</b>
3.1	Namespace List . . . . .	5
<b>4</b>	<b>Hierarchical Index</b>	<b>7</b>
4.1	Class Hierarchy . . . . .	7
<b>5</b>	<b>Class Index</b>	<b>9</b>
5.1	Class List . . . . .	9

<b>6</b>	<b>Namespace Documentation</b>	<b>11</b>
6.1	IpxCam Namespace Reference	11
6.1.1	Detailed Description	12
6.1.2	Typedef Documentation	12
6.1.2.1	InterfaceList	12
6.1.2.2	DeviceInfoList	12
6.1.2.3	DeviceList	13
6.1.2.4	EventCallback	13
6.1.2.5	EventCallback2	13
6.1.3	Enumeration Type Documentation	13
6.1.3.1	InterfaceType	13
6.1.3.2	FlushOperation	14
6.1.3.3	DeviceAccess	14
6.1.4	Function Documentation	14
6.1.4.1	IpxCam_GetSystem()	14
6.2	IpxGenParam Namespace Reference	15
6.2.1	Detailed Description	16
6.2.2	Enumeration Type Documentation	16
6.2.2.1	ParamType	16
6.2.2.2	NameSpace	17
6.2.2.3	Visibility	17
6.3	IpxGui Namespace Reference	17
6.3.1	Detailed Description	19
6.3.2	Enumeration Type Documentation	19
6.3.2.1	Visibility	19
6.3.3	Function Documentation	19
6.3.3.1	CreateGenParamTreeViewForArrayA()	19
6.3.3.2	CreateGenParamTreeViewForArrayW()	20
6.3.3.3	CreateGenParamTreeViewForNodemapA()	21
6.3.3.4	CreateGenParamTreeViewForNodemapW()	22
6.3.3.5	DestroyGenParamTreeView()	23
6.3.3.6	SelectCameraA()	24
6.3.3.7	SelectCameraW()	24
6.3.3.8	ShowCamConfigDialog()	25
6.3.3.9	ShowFrameABDialog()	26
6.3.3.10	ShowTriggerDialog()	26
6.3.3.11	ShowPulseDialog()	27
6.3.3.12	ShowStrobeDialog()	28
6.3.3.13	ShowOutputDialog()	28
6.3.3.14	ShowColorDialog()	29

<b>7</b>	<b>Class Documentation</b>	<b>31</b>
7.1	IpxGenParam::Array Class Reference	31
7.1.1	Detailed Description	32
7.1.2	Constructor & Destructor Documentation	33
7.1.2.1	~Array()	33
7.1.3	Member Function Documentation	33
7.1.3.1	GetParam()	33
7.1.3.2	GetBoolean()	34
7.1.3.3	GetCommand()	34
7.1.3.4	GetEnum()	35
7.1.3.5	GetFloat()	35
7.1.3.6	GetInt()	36
7.1.3.7	GetString()	36
7.1.3.8	GetRootCategory()	37
7.1.3.9	GetNodeMap()	37
7.1.3.10	GetCount()	38
7.1.3.11	GetParamByIndex()	38
7.1.3.12	SetBooleanValue()	38
7.1.3.13	GetBooleanValue()	39
7.1.3.14	SetEnumValueStr()	39
7.1.3.15	SetEnumValue()	40
7.1.3.16	GetEnumValueStr()	40
7.1.3.17	GetEnumValue()	41
7.1.3.18	SetFloatValue()	41
7.1.3.19	GetFloatValue()	42
7.1.3.20	SetIntegerValue()	43
7.1.3.21	GetIntegerValue()	43
7.1.3.22	SetStringValue()	44

7.1.3.23	GetStringValue()	44
7.1.3.24	ExecuteCommand()	45
7.1.3.25	IsCommandDone()	45
7.1.3.26	Poll()	46
7.2	IpxGenParam::Boolean Class Reference	46
7.2.1	Detailed Description	47
7.2.2	Member Function Documentation	47
7.2.2.1	GetType()	47
7.2.2.2	SetValue()	47
7.2.2.3	GetValue()	48
7.3	IpxCam::Buffer Class Reference	48
7.3.1	Detailed Description	49
7.3.2	Constructor & Destructor Documentation	50
7.3.2.1	~Buffer()	50
7.3.3	Member Function Documentation	50
7.3.3.1	GetImage()	50
7.3.3.2	GetBufferPtr()	50
7.3.3.3	GetImageOffset()	51
7.3.3.4	GetBufferSize()	51
7.3.3.5	GetPixelFormat()	51
7.3.3.6	GetUserPtr()	51
7.3.3.7	GetTimestamp()	52
7.3.3.8	GetFrameID()	52
7.3.3.9	IsIncomplete()	52
7.3.3.10	GetWidth()	53
7.3.3.11	GetHeight()	53
7.3.3.12	GetXOffset()	53
7.3.3.13	GetYOffset()	54

7.3.3.14	<a href="#">GetXPadding()</a>	54
7.3.3.15	<a href="#">GetYPadding()</a>	54
7.3.3.16	<a href="#">GetDeliveredHeight()</a>	54
7.3.3.17	<a href="#">IsKacFrameB()</a>	55
7.4	<a href="#">IpxGenParam::Category Class Reference</a>	55
7.4.1	<a href="#">Detailed Description</a>	56
7.4.2	<a href="#">Member Function Documentation</a>	56
7.4.2.1	<a href="#">GetType()</a>	56
7.4.2.2	<a href="#">GetCount()</a>	56
7.4.2.3	<a href="#">GetParamByIndex()</a>	56
7.5	<a href="#">IpxGenParam::Command Class Reference</a>	57
7.5.1	<a href="#">Detailed Description</a>	58
7.5.2	<a href="#">Member Function Documentation</a>	58
7.5.2.1	<a href="#">GetType()</a>	58
7.5.2.2	<a href="#">Execute()</a>	58
7.5.2.3	<a href="#">IsDone()</a>	58
7.6	<a href="#">IpxCam::Device Class Reference</a>	59
7.6.1	<a href="#">Detailed Description</a>	60
7.6.2	<a href="#">Member Enumeration Documentation</a>	60
7.6.2.1	<a href="#">UploadEventType</a>	61
7.6.2.2	<a href="#">Endianness</a>	62
7.6.3	<a href="#">Constructor &amp; Destructor Documentation</a>	62
7.6.3.1	<a href="#">~Device()</a>	62
7.6.4	<a href="#">Member Function Documentation</a>	62
7.6.4.1	<a href="#">GetNumStreams()</a>	62
7.6.4.2	<a href="#">GetStreamByIndex()</a>	63
7.6.4.3	<a href="#">GetStreamById()</a>	63
7.6.4.4	<a href="#">GetInfo()</a>	63

7.6.4.5	ReadMem()	64
7.6.4.6	WriteMem()	64
7.6.4.7	RegisterEvent2()	65
7.6.4.8	RegisterEvent()	65
7.6.4.9	UnRegisterEvent2()	65
7.6.4.10	UnRegisterEvent()	66
7.6.4.11	GetTransportParameters()	66
7.6.4.12	GetCameraParameters()	67
7.6.4.13	SaveConfiguration()	67
7.6.4.14	LoadConfiguration()	67
7.6.4.15	GetEndianness()	68
7.7	IpxCam::DeviceInfo Class Reference	68
7.7.1	Detailed Description	69
7.7.2	Constructor & Destructor Documentation	69
7.7.2.1	~DeviceInfo()	69
7.7.3	Member Function Documentation	70
7.7.3.1	GetInterface()	70
7.7.3.2	GetID()	70
7.7.3.3	GetVendor()	70
7.7.3.4	GetModel()	71
7.7.3.5	GetDisplayName()	71
7.7.3.6	GetUserDefinedName()	71
7.7.3.7	GetSerialNumber()	71
7.7.3.8	GetVersion()	72
7.7.3.9	GetAccessStatus()	72
7.7.3.10	GetUSB3HostInfo()	72
7.7.3.11	GetIPAddress()	72
7.7.3.12	GetIPMask()	73



7.7.3.13	GetIPGateway()	73
7.7.3.14	GetIP()	74
7.7.3.15	ForceIP() [1/2]	74
7.7.3.16	ForceIP() [2/2]	75
7.8	IpxGenParam::Enum Class Reference	75
7.8.1	Detailed Description	76
7.8.2	Member Function Documentation	77
7.8.2.1	GetType()	77
7.8.2.2	GetEnumEntriesCount()	77
7.8.2.3	GetEnumEntryByIndex()	77
7.8.2.4	GetEnumEntryByName()	79
7.8.2.5	GetEnumEntryByValue()	79
7.8.2.6	GetValue()	80
7.8.2.7	GetValueStr()	80
7.8.2.8	SetValue()	81
7.8.2.9	SetValueStr()	81
7.9	IpxGenParam::EnumEntry Class Reference	81
7.9.1	Detailed Description	82
7.9.2	Member Function Documentation	82
7.9.2.1	GetType()	83
7.9.2.2	GetValue()	83
7.9.2.3	GetValueStr()	83
7.10	IpxGenParam::Float Class Reference	84
7.10.1	Detailed Description	85
7.10.2	Member Function Documentation	85
7.10.2.1	GetType()	85
7.10.2.2	SetValue()	85
7.10.2.3	GetValue()	86

7.10.2.4	<a href="#">GetMin()</a>	86
7.10.2.5	<a href="#">GetMax()</a>	87
7.10.2.6	<a href="#">GetUnit()</a>	87
7.11	<a href="#">IpxGui::IpxGenParamTreeView Class Reference</a>	88
7.11.1	<a href="#">Detailed Description</a>	89
7.11.2	<a href="#">Constructor &amp; Destructor Documentation</a>	89
7.11.2.1	<a href="#">~IpxGenParamTreeView()</a>	89
7.11.3	<a href="#">Member Function Documentation</a>	90
7.11.3.1	<a href="#">setParams() [1/2]</a>	91
7.11.3.2	<a href="#">setParams() [2/2]</a>	91
7.11.3.3	<a href="#">clearParams()</a>	92
7.11.3.4	<a href="#">visibility()</a>	92
7.11.3.5	<a href="#">setVisibility()</a>	93
7.11.3.6	<a href="#">saveState()</a>	93
7.11.3.7	<a href="#">loadState()</a>	93
7.11.3.8	<a href="#">setPollingTime()</a>	94
7.11.3.9	<a href="#">getPollingTime()</a>	94
7.12	<a href="#">IpxGenParam::Int Class Reference</a>	95
7.12.1	<a href="#">Detailed Description</a>	95
7.12.2	<a href="#">Member Function Documentation</a>	96
7.12.2.1	<a href="#">GetType()</a>	96
7.12.2.2	<a href="#">SetValue()</a>	96
7.12.2.3	<a href="#">GetValue()</a>	96
7.12.2.4	<a href="#">GetMin()</a>	97
7.12.2.5	<a href="#">GetMax()</a>	97
7.12.2.6	<a href="#">GetIncrement()</a>	98
7.13	<a href="#">IpxCam::Interface Class Reference</a>	98
7.13.1	<a href="#">Detailed Description</a>	99

7.13.2	Constructor & Destructor Documentation	99
7.13.2.1	~Interface()	100
7.13.3	Member Function Documentation	100
7.13.3.1	GetDeviceInfoList()	100
7.13.3.2	GetFirstDeviceInfo()	101
7.13.3.3	GetDeviceInfoById()	101
7.13.3.4	ReEnumerateDevices()	101
7.13.3.5	GetDescription()	102
7.13.3.6	GetType()	102
7.13.3.7	GetId()	103
7.13.3.8	GetVersion()	103
7.13.3.9	RegisterEvent2()	103
7.13.3.10	RegisterEvent()	104
7.13.3.11	UnRegisterEvent2()	104
7.13.3.12	UnRegisterEvent()	104
7.13.3.13	GetParameters()	105
7.13.3.14	CreateDeviceFromConfig()	105
7.14	IpxCam::List<_T> Class Template Reference	106
7.14.1	Detailed Description	106
7.14.2	Member Typedef Documentation	108
7.14.2.1	elem_type	108
7.14.3	Constructor & Destructor Documentation	108
7.14.3.1	~List()	108
7.14.4	Member Function Documentation	108
7.14.4.1	Release()	109
7.14.4.2	GetCount()	109
7.14.4.3	GetFirst()	109
7.14.4.4	GetNext()	109

7.15 IpxGenParam::Param Class Reference . . . . .	110
7.15.1 Detailed Description . . . . .	111
7.15.2 Constructor & Destructor Documentation . . . . .	112
7.15.2.1 ~Param() . . . . .	112
7.15.3 Member Function Documentation . . . . .	112
7.15.3.1 GetType() . . . . .	112
7.15.3.2 GetName() . . . . .	112
7.15.3.3 GetToolTip() . . . . .	113
7.15.3.4 GetDescription() . . . . .	113
7.15.3.5 GetDisplayName() . . . . .	113
7.15.3.6 GetVisibility() . . . . .	113
7.15.3.7 IsValueCached() . . . . .	114
7.15.3.8 IsAvailable() . . . . .	114
7.15.3.9 IsWritable() . . . . .	114
7.15.3.10 IsReadable() . . . . .	114
7.15.3.11 IsStreamable() . . . . .	115
7.15.3.12 IsVisible() . . . . .	115
7.15.3.13 RegisterEventSink() . . . . .	115
7.15.3.14 UnregisterEventSink() . . . . .	116
7.15.3.15 GetNode() . . . . .	116
7.15.3.16 ToCategory() . . . . .	116
7.15.3.17 ToBoolean() . . . . .	117
7.15.3.18 ToCommand() . . . . .	117
7.15.3.19 ToEnumEntry() . . . . .	117
7.15.3.20 ToEnum() . . . . .	117
7.15.3.21 ToFloat() . . . . .	118
7.15.3.22 ToInt() . . . . .	118
7.15.3.23 ToString() . . . . .	118

7.16 IpxGenParam::ParamEventSink Class Reference . . . . .	118
7.16.1 Detailed Description . . . . .	119
7.16.2 Member Function Documentation . . . . .	119
7.16.2.1 OnParameterUpdate() . . . . .	119
7.17 IpxCam::Stream Class Reference . . . . .	119
7.17.1 Detailed Description . . . . .	121
7.17.2 Constructor & Destructor Documentation . . . . .	121
7.17.2.1 ~Stream() . . . . .	121
7.17.3 Member Function Documentation . . . . .	121
7.17.3.1 Release() . . . . .	121
7.17.3.2 CreateBuffer() . . . . .	121
7.17.3.3 SetBuffer() . . . . .	122
7.17.3.4 RevokeBuffer() . . . . .	122
7.17.3.5 QueueBuffer() . . . . .	123
7.17.3.6 GetBuffer() . . . . .	123
7.17.3.7 CancelBuffer() . . . . .	124
7.17.3.8 FlushBuffers() . . . . .	124
7.17.3.9 StartAcquisition() . . . . .	124
7.17.3.10 StopAcquisition() . . . . .	125
7.17.3.11 AllocBufferQueue() . . . . .	125
7.17.3.12 ReleaseBufferQueue() . . . . .	126
7.17.3.13 GetBufferQueueSize() . . . . .	126
7.17.3.14 RegisterEvent() . . . . .	126
7.17.3.15 UnRegisterEvent() . . . . .	127
7.17.3.16 GetParameters() . . . . .	127
7.17.3.17 GetNumDelivered() . . . . .	128
7.17.3.18 GetNumUnderrun() . . . . .	128
7.17.3.19 GetNumAnnounced() . . . . .	128

7.17.3.20	GetNumQueued()	129
7.17.3.21	GetNumAwaitDelivery()	129
7.17.3.22	GetBufferSize()	129
7.17.3.23	IsGrabbing()	130
7.17.3.24	GetMinNumBuffers()	130
7.17.3.25	GetBufferAlignment()	130
7.18	IpxGenParam::String Class Reference	131
7.18.1	Detailed Description	131
7.18.2	Member Function Documentation	131
7.18.2.1	GetType()	132
7.18.2.2	GetMaxLength()	132
7.18.2.3	GetValue()	132
7.18.2.4	SetValue()	133
7.19	IpxCam::System Class Reference	133
7.19.1	Detailed Description	134
7.19.2	Constructor & Destructor Documentation	135
7.19.2.1	~System()	135
7.19.3	Member Function Documentation	135
7.19.3.1	Release()	135
7.19.3.2	GetInterfaceList()	136
7.19.3.3	GetInterfaceById()	137
7.19.3.4	GetDisplayName()	137
7.19.3.5	GetVersion()	138
7.19.3.6	CreateDeviceFromConfig()	138
7.19.3.7	RegisterGenTLProvider()	139

# Chapter 1

## Imperx Camera C++ SDK

### 1.1 General Information

The Imperx Camera C++ SDK is designed to provide software developers with C++ API functionality for ease of integrating Imperx cameras into their software applications. The API implemented in two libraries: `lpxCameraApi` and `lpxCameraGuiApi`. `lpxCameraApi` includes two namespaces: `lpxCam` and `lpxGenParam`. `lpxCameraGuiApi` includes `lpxGui` namespace.

The `lpxCam` namespace provides the scope to the API of GenICam GenTL transport layer to acquire images with an Imperx Camera. The `lpxGenParam` namespace provides the scope to the API to control the GenICam camera parameters, like image Width, Height, Pixel Format, Gain, Exposure, Trigger settings, etc. `lpxGui` namespace provides the scope for the user interface features, like windows and panels.

### 1.2 lpxCameraApi library

`lpxCameraApi` library includes classes, functions and types of `lpxCam` and `lpxGenParam` namespaces. It uses Imperx GenTL Producer library `lpxCTI.cti` to communicate with the cameras

#### 1.2.1 lpxCam namespace

The `lpxCam` namespace consist of several main classes that represent the GenTL modules. The main classes are

- `lpxCam::System` - The System class is the entry point to the GenTL Producer software driver.
- `lpxCam::Interface` - The Interface class provides method to represents an individual physical interface, like GigE or USB3
- `lpxCam::Device` - The Device class provides methods to enable the communication with the camera device and enumerate/instantiate the video data streams.

- [IpxCam::Stream](#) - The Stream class purpose is to access the image buffer data acquirement from the Acquisition engine.
- [IpxCam::Buffer](#) - The Buffer class contains the methods to access the image data and parameters of the acquired image buffer.

### Example of GenTL System Hierarchy

#### 1.2.2 IpxGenParam namespace

The [IpxGenParam](#) namespace consist of the following main classes to access the GenICam parameters features. The main classes are

- [IpxGenParam::Param](#) - General class for accessing the GenICam feature node of the Camera parameters.
- [IpxGenParam::Boolean](#) - Class representing the Boolean GenICam camera parameter.
- [IpxGenParam::Command](#) - Class representing the Command GenICam camera parameter.
- [IpxGenParam::Enum](#) - Class representing the Enumeration GenICam camera parameter.
- [IpxGenParam::Float](#) - Class representing the Float GenICam camera parameter.
- [IpxGenParam::Int](#) - Class representing the Integer GenICam camera parameter.
- [IpxGenParam::String](#) - Class representing the String GenICam camera parameter.

### 1.3 IpxCameraGuiApi library

IpxCameraGuiApi library includes classes, functions and types of [IpxGui](#) namespace. The [IpxGui](#) namespace consist of the following GUI API classes and functions:

- [IpxGui::SelectCameraA](#) - function to show the modal dialog window of camera selection
- [IpxGui::SelectCameraW](#) - unicode version of [IpxGui::SelectCameraA](#)
- [IpxGui::CreateGenParamTreeViewForArrayA](#) - function to show the modeless dialog window of the camera GenICam parameters
- [IpxGui::CreateGenParamTreeViewForArrayW](#) - unicode version of [IpxGui::CreateGenParamTreeViewForArrayA](#)
- [IpxGui::DestroyGenParamTreeView](#) - function to destroy the modeless dialog window of the camera GenICam parameters, created with [IpxGui::CreateGenParamTreeViewForArrayA](#) function call
- [IpxGui::IpxGenParamTreeView](#) - Interface class for the modeless dialog window of the camera GenICam parameters. This class provides methods to set visibility level and parameters tree state.
- [IpxGui::IpxGenParamTreeView](#) - QT class, based on QWidget for the modeless window of the camera GenICam parameters.
- [IpxGui::IpxCameraSelectorDialog](#) - QT class, based on QDialog for the modal dialog window of camera selection



## Chapter 2

# Deprecated List

**Member [lpxCam::Device::RegisterEvent](#)** (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0

Use [Device::RegisterEvent2](#) instead

**Member [lpxCam::Device::UnRegisterEvent](#)** (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0

Use [Device::UnRegisterEvent2](#) instead

**Member [lpxCam::EventCallback](#)** (const void \*eventData, size\_t eventSize, void \*pPrivate)

Use [EventCallback2](#) instead

**Member [lpxCam::Interface::RegisterEvent](#)** (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0

Use [RegisterEvent2](#) instead

**Member [lpxCam::Interface::UnRegisterEvent](#)** (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0

Use [UnRegisterEvent2](#) instead



## Chapter 3

# Namespace Index

### 3.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

<a href="#">lpxCam</a>	A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera . . . . .	11
<a href="#">lpxGenParam</a>	A namespace provides the scope to the API to access the GenICam parameters . . . . .	15
<a href="#">lpxGui</a>	The lpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions . . . . .	17



## Chapter 4

# Hierarchical Index

### 4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

IpxGenParam::Array . . . . .	31
IpxCam::Buffer . . . . .	48
IpxCam::Device . . . . .	59
IpxCam::DeviceInfo . . . . .	68
IpxGui::IpxGenParamTreeView . . . . .	88
IpxCam::Interface . . . . .	98
IpxCam::List<_T> . . . . .	106
IpxGenParam::Param . . . . .	110
IpxGenParam::Boolean . . . . .	46
IpxGenParam::Category . . . . .	55
IpxGenParam::Command . . . . .	57
IpxGenParam::Enum . . . . .	75
IpxGenParam::EnumEntry . . . . .	81
IpxGenParam::Float . . . . .	84
IpxGenParam::Int . . . . .	95
IpxGenParam::String . . . . .	131
IpxGenParam::ParamEventSink . . . . .	118
IpxCam::Stream . . . . .	119
IpxCam::System . . . . .	133



## Chapter 5

# Class Index

### 5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

<a href="#">lpxGenParam::Array</a>	31
An <a href="#">Array</a> class contains methods to access all GenICam camera parameters . . . . .	
<a href="#">lpxGenParam::Boolean</a>	46
A class containing methods for <a href="#">Boolean</a> GenICam camera parameter . . . . .	
<a href="#">lpxCam::Buffer</a>	48
<a href="#">Buffer</a> module in the GenTL module hierarchy . . . . .	
<a href="#">lpxGenParam::Category</a>	55
A class containing methods for GenICam <a href="#">Category</a> . . . . .	
<a href="#">lpxGenParam::Command</a>	57
A class containing methods for <a href="#">Command</a> GenICam camera parameter . . . . .	
<a href="#">lpxCam::Device</a>	59
<a href="#">Device</a> module in the GenTL module hierarchy . . . . .	
<a href="#">lpxCam::DeviceInfo</a>	68
<a href="#">DeviceInfo</a> class provides the information about the camera device . . . . .	
<a href="#">lpxGenParam::Enum</a>	75
A class containing methods for Enumeration GenICam camera parameter . . . . .	
<a href="#">lpxGenParam::EnumEntry</a>	81
<a href="#">EnumEntry</a> class represents the entry of GenICam <a href="#">Enum</a> parameter . . . . .	
<a href="#">lpxGenParam::Float</a>	84
A class containing methods for <a href="#">Float</a> GenICam camera parameter . . . . .	
<a href="#">lpxGui::IlpxGenParamTreeView</a>	88
<a href="#">IlpxGenParamTreeView</a> class represents the GenICam parameters node tree panel . . . . .	
<a href="#">lpxGenParam::Int</a>	95
A class containing methods for Integer GenICam camera parameter . . . . .	
<a href="#">lpxCam::Interface</a>	98
<a href="#">Interface</a> module in the GenTL module hierarchy . . . . .	
<a href="#">lpxCam::List&lt;_T&gt;</a>	106
The <a href="#">List</a> class is used as list-like container for the specified template type objects . . . . .	
<a href="#">lpxGenParam::Param</a>	110
General class for GenICam parameter . . . . .	
<a href="#">lpxGenParam::ParamEventSink</a>	118
A Class for <a href="#">ParamEventSink</a> notifications handling . . . . .	

<a href="#">lpxCam::Stream</a>	
Data stream module in the GenTL module hierarchy . . . . .	<a href="#">119</a>
<a href="#">lpxGenParam::String</a>	
A class containing methods for <a href="#">String</a> GenlCam camera parameter . . . . .	<a href="#">131</a>
<a href="#">lpxCam::System</a>	
Abstraction of the <a href="#">System</a> module of the GenTL module hierarchy . . . . .	<a href="#">133</a>



## Chapter 6

# Namespace Documentation

### 6.1 IpxCam Namespace Reference

A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera.

#### Classes

- class [Buffer](#)  
*The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.*
- class [Device](#)  
*The [Device](#) class represents the device module in the GenTL module hierarchy.*
- class [DeviceInfo](#)  
*[DeviceInfo](#) class provides the information about the camera device.*
- class [Interface](#)  
*The [Interface](#) class represents a interface module in the GenTL module hierarchy.*
- class [List](#)  
*The [List](#) class is used as list-like container for the specified template type objects.*
- class [Stream](#)  
*The [Stream](#) class represents the data stream module in the GenTL module hierarchy.*
- class [System](#)  
*The [System](#) class represents an abstraction of the [System](#) module of the GenTL module hierarchy.*

#### Typedefs

- typedef [List](#)< [Interface](#) > [InterfaceList](#)
- typedef [List](#)< [DeviceInfo](#) > [DeviceInfoList](#)
- typedef [List](#)< [Device](#) > [DeviceList](#)
- typedef void IPXCAM\_CALL [EventCallback](#)(const void \*eventData, size\_t eventSize, void \*pPrivate)
- typedef void IPXCAM\_CALL [EventCallback2](#)(uint32\_t eventType, const void \*eventData, size\_t eventSize, void \*pPrivate)  
*[EventCallback2](#).*

## Enumerations

- enum [InterfaceType](#) : uint32\_t {  
[USB3Vision](#) = 1, [GigEVision](#) = 2, [CameraLink](#) = 3, [CoaxPress](#) = 4,  
[HdSdi](#) = 5, [AllInterfaces](#) = 0xff }  
*An enum of Interface Types. Interface Node Types representing physical interface in the system.*
- enum [FlushOperation](#) : uint32\_t { [Flush\\_OutputDiscard](#) = 1, [Flush\\_AllToInput](#) = 2, [Flush\\_UnqueuedToInput](#) = 3,  
[Flush\\_AllDiscard](#) = 4 }  
*An enum of Flush Operations. Flush Operations Types.*
- enum [DeviceAccess](#) : uint32\_t { [ReadOnly](#) = 0, [Control](#) = 1, [Exclusive](#) = 2 }  
*An enum of Device Access.*

## Functions

- IPXCAM\_EXTERN\_C IPX\_CAMERA\_API [System](#) \* [IpxCam\\_GetSystem](#) ()  
*Returns the [System](#) object pointer.*

### 6.1.1 Detailed Description

A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera.

[IpxCam](#) namespace includes classes that represent the base GenTLtransport layer modules: [System](#), [Interface](#), [Device](#), [Stream](#), [Buffer](#). These modules can be used to enumerate the interfaces in the system, enumerate the cameras, connected to each interface, connect to necessary camera, allocate the memory buffers for images, and run the video acquisition.

### 6.1.2 Typedef Documentation

#### 6.1.2.1 InterfaceList

```
typedef List<Interface> IpxCam::InterfaceList
```

[List](#) of [Interface](#) objects

#### 6.1.2.2 DeviceInfoList

```
typedef List<DeviceInfo> IpxCam::DeviceInfoList
```

[List](#) of [DeviceInfo](#) objects

### 6.1.2.3 DeviceList

```
typedef List<Device> IpxCam::DeviceList
```

List of [Device](#) objects

### 6.1.2.4 EventCallback

```
typedef void IPXCAM_CALL IpxCam::EventCallback(const void *eventData, size_t eventSize, void *pPrivate)
```

EventCallback

**Deprecated** Use EventCallback2 instead

### 6.1.2.5 EventCallback2

```
typedef void IPXCAM_CALL IpxCam::EventCallback2(uint32_t eventType, const void *eventData, size_t eventSize, void *pPrivate)
```

EventCallback2.

Callback function type for Event handling param[in] eventType type of the arrived event param[in] eventData pointer to event Data param[in] eventSize event Size param[in] pPrivate pointer to the context Data

## 6.1.3 Enumeration Type Documentation

### 6.1.3.1 InterfaceType

```
enum IpxCam::InterfaceType : uint32_t
```

An enum of [Interface](#) Types. [Interface](#) Node Types representing physical interface in the system.

Enumerator

USB3Vision	Enum value for USB3Vision camera interface.
GigEVision	Enum value for GigEVision camera interface
CameraLink	Enum value for CameraLink camera interface
CoaxPress	Enum value for CoaxPress camera interface
HdSdi	Enum value for HD-SDI camera interface
AllInterfaces	Enum value AllInterfaces.

Generated by Doxygen

### 6.1.3.2 FlushOperation

```
enum IpxCam::FlushOperation : uint32_t
```

An enum of Flush Operations. Flush Operations Types.

#### Enumerator

Flush_OutputDiscard	Enum value Flush_OutputDiscard. Discards all buffers in the output queue and if necessary remove the entries from the event data queue.
Flush_AllToInput	Enum value Flush_AllToInput. Puts all buffers in the input pool. Even those in the output queue and discard entries in the event data queue.
Flush_UnqueuedToInput	Enum value Flush_UnqueuedToInput. Puts all buffers that are not in the input pool or the output queue in the input pool.
Flush_AllDiscard	Enum value Flush_AllDiscard. Discards all buffers in the input pool and output queue.

### 6.1.3.3 DeviceAccess

```
enum IpxCam::DeviceAccess : uint32_t
```

An enum of [Device](#) Access.

#### Enumerator

ReadOnly	Enum value ReadOnly.
Control	Enum value Control.
Exclusive	Enum value Exclusive.

## 6.1.4 Function Documentation

### 6.1.4.1 IpxCam\_GetSystem()

```
IPXCAM_EXTERN_C IPX_CAMERA_API System* IpxCam::IpxCam_GetSystem ( )
```

Returns the [System](#) object pointer.

This method returns the [System](#) module object. [System](#) object is being created as soon as API library is loaded. It is the entry point to the GenTL Module hierarchy.

## Returns

Returns the pointer to system.

Here is the caller graph for this function:



## 6.2 IpxGenParam Namespace Reference

A namespace provides the scope to the API to access the GenICam parameters.

### Classes

- class [Array](#)  
An [Array](#) class contains methods to access all GenICam camera parameters.
- class [Boolean](#)  
A class containing methods for [Boolean](#) GenICam camera parameter.
- class [Category](#)  
A class containing methods for GenICam [Category](#).
- class [Command](#)  
A class containing methods for [Command](#) GenICam camera parameter.
- class [Enum](#)  
A class containing methods for Enumeration GenICam camera parameter.
- class [EnumEntry](#)  
[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.
- class [Float](#)  
A class containing methods for [Float](#) GenICam camera parameter.
- class [Int](#)  
A class containing methods for Integer GenICam camera parameter.
- class [Param](#)  
General class for GenICam parameter.
- class [ParamEventSink](#)  
A Class for [ParamEventSink](#) notifications handling.
- class [String](#)  
A class containing methods for [String](#) GenICam camera parameter.

## Enumerations

- enum [ParamType](#) : uint32\_t {  
[ParamUnknown](#), [ParamInt](#), [ParamFloat](#), [ParamString](#),  
[ParamEnum](#), [ParamEnumEntry](#), [ParamBoolean](#), [ParamCommand](#),  
[ParamCategory](#) }  
*An enumeration of Parameter Types. Parameter Node Types that can access the node object's programming interface.*
- enum [NameSpace](#) : uint32\_t { [NameSpaceStandard](#) = 0, [NameSpaceCustom](#), [NameSpaceUndefined](#) =999 }  
*An enumeration of GenICam NameSpace. Parameter Node Namespace.*
- enum [Visibility](#) : uint32\_t {  
[VisBeginner](#) = 0, [VisExpert](#), [VisGuru](#), [VisInvisible](#),  
[VisUndefined](#) = 99 }  
*An enumeration of Visibility. This element defines the level of user that has access to the feature.*

### 6.2.1 Detailed Description

A namespace provides the scope to the API to access the GenICam parameters.

The [IpxGenParam](#) namespace provides the scope to the API to control the GenICam camera parameters of types: [Boolean](#), Enumeration, [String](#), [Float](#), Integer, Commands and Categories. Such parameters may include image Width, Height, Pixel Format, Gain, Exposure, Trigger, I/O settings, etc. Parameters are described in camera GenICam XML file, and documented in appropriate camera user's manual.

### 6.2.2 Enumeration Type Documentation

#### 6.2.2.1 ParamType

```
enum IpxGenParam::ParamType : uint32_t
```

An enumeration of Parameter Types. Parameter Node Types that can access the node object's programming interface.

#### Enumerator

<a href="#">ParamUnknown</a>	<a href="#">Enum</a> value <a href="#">ParamUnknown</a> . Unknown Parameter.
<a href="#">ParamInt</a>	<a href="#">Enum</a> value <a href="#">ParamInt</a> will access node object's of <a href="#">Integer</a> interface.
<a href="#">ParamFloat</a>	<a href="#">Enum</a> value <a href="#">ParamFloat</a> will access node object's of <a href="#">IFloat</a> interface.
<a href="#">ParamString</a>	<a href="#">Enum</a> value <a href="#">ParamString</a> will access node object's of <a href="#">IString</a> interface.
<a href="#">ParamEnum</a>	<a href="#">Enum</a> value <a href="#">ParamEnum</a> will access node object's of <a href="#">IEnumeration</a> interface.
<a href="#">ParamEnumEntry</a>	<a href="#">Enum</a> value <a href="#">ParamEnumEntry</a> will access the entry of <a href="#">Enum</a> parameter.
<a href="#">ParamBoolean</a>	<a href="#">Enum</a> value <a href="#">ParamBoolean</a> will access node object's of <a href="#">IBoolean</a> interface.
<a href="#">ParamCommand</a>	<a href="#">Enum</a> value <a href="#">ParamCommand</a> will access node object's of <a href="#">ICommand</a> interface.
<a href="#">ParamCategory</a>	<a href="#">Enum</a> value <a href="#">ParamCategory</a> will access node object's of <a href="#">ICategory</a> interface.

### 6.2.2.2 Namespace

```
enum IpxGenParam::NameSpace : uint32_t
```

An enumeration of GenICam NameSpace. Parameter Node Namespace.

#### Enumerator

NameSpaceStandard	<a href="#">Enum</a> value NameSpaceStandard. Identifies the standard namespace used in the file.
NameSpaceCustom	<a href="#">Enum</a> value NameSpaceCustom. Identifies the custom namespace used in the file.
NameSpaceUndefined	<a href="#">Enum</a> value NameSpaceUndefined. Unknown namespace.

### 6.2.2.3 Visibility

```
enum IpxGenParam::Visibility : uint32_t
```

An enumeration of Visibility. This element defines the level of user that has access to the feature.

#### Enumerator

VisBeginner	<a href="#">Enum</a> value VisBeginner. User has visibility to all the basic features of the device.
VisExpert	<a href="#">Enum</a> value VisExpert. User has visibility to more advance features of the device.
VisGuru	<a href="#">Enum</a> value VisGuru. User has visibility to even more advance features that if set improperly can cause device to be in an improper state.
VisInvisible	<a href="#">Enum</a> value VisInvisible. Not visible.
VisUndefined	<a href="#">Enum</a> value VisUndefined. Unknown visibility.

## 6.3 IpxGui Namespace Reference

The IpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions.

### Classes

- class [IpxGenParamTreeView](#)

*[IpxGenParamTreeView](#) class represents the GenICam parameters node tree panel.*

## Enumerations

- enum [Visibility](#) : uint32\_t { [Beginner](#) = 0, [Expert](#), [Guru](#) }

*An enum of Visibility. Defines the visibility type of features that user will see in the Tree View.*

## Functions

- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxGenParamTreeView](#) \* [CreateGenParamTreeViewForArrayA](#) ([IpxGenParam::Array](#) \*genParam, const char \*title, uintptr\_t parentWindow=0)  
*Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxGenParamTreeView](#) \* [CreateGenParamTreeViewForArrayW](#) ([IpxGenParam::Array](#) \*genParam, const wchar\_t \*title, uintptr\_t parentWindow=0)  
*Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object. Unicode version.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxGenParamTreeView](#) \* [CreateGenParamTreeViewForNodemapA](#) (IPX\_GENAPI\_NS::INodeMap \*nodemap, const char \*title, uintptr\_t parentWindow=0)  
*Creates the panel of the camera GenICam parameters for [GenApi::INodeMap](#) object.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxGenParamTreeView](#) \* [CreateGenParamTreeViewForNodemapW](#) (IPX\_GENAPI\_NS::INodeMap \*nodemap, const wchar\_t \*title, uintptr\_t parentWindow=0)  
*Creates the panel of the camera GenICam parameters for [GenApi::INodeMap](#) object. Unicode version.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [DestroyGenParamTreeView](#) ([IpxGenParamTreeView](#) \*view)  
*Destroys the GenICam parameters panel.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxCam::DeviceInfo](#) \* [SelectCameraA](#) ([IpxCam::System](#) \*pSystem, const char \*title, uintptr\_t parentWindow=0, bool poll=true)  
*Pops-up the camera selection dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API [IpxCam::DeviceInfo](#) \* [SelectCameraW](#) ([IpxCam::System](#) \*pSystem, const wchar\_t \*title, uintptr\_t parentWindow=0, bool poll=true)  
*Pops-up the camera selection dialog. Unicode version.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowCamConfigDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Camera Configuration Dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowFrameABDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowTriggerDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Trigger Dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowPulseDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Pulse Dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowStrobeDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Strobe Dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowOutputDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Output Data Dialog.*
- IPXCAM\_GUI\_EXTERN\_C IPX\_CAMERA\_GUI\_API void [ShowColorDialog](#) ([IpxCam::Device](#) \*device, uintptr\_t parentWindow=0)  
*Show Color Dialog.*



### 6.3.1 Detailed Description

The IpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions.

The IpxGUI namespace includes Imperx Camera GUI API classes and functions, such as: [IpxGenParamTreeView](#), [SelectCameraA](#) [SelectCameraW](#) [IpxGenParamTreeView](#), [IpxCameraSelectorDialog](#)

### 6.3.2 Enumeration Type Documentation

#### 6.3.2.1 Visibility

```
enum IpxGui::Visibility : uint32_t
```

An enum of Visibility. Defines the visibility type of features that user will see in the Tree View.

Enumerator

Beginner	Enum value Beginner. User has visibility to all the basic features of the device.
Expert	Enum value Expert. User has visibility to more advance features of the device.
Guru	Enum value Guru. User has visibility to even more advance features that if set improperly can cause device to be in an improper state.

### 6.3.3 Function Documentation

#### 6.3.3.1 CreateGenParamTreeViewForArrayA()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxGenParamTreeView* IpxGui::CreateGenParamTreeViewFor↵
ArrayA (
    IpxGenParam::Array * genParam,
    const char * title,
    uintptr_t parentWindow = 0 )
```

Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object.

This function returns the pointer to the [IpxGenParamTreeView](#) class that was created using information extracted from the [IpxGenParam::Array](#) class.

## Parameters

in	<i>genParam</i>	The pointer to the <a href="#">IpxGenParam::Array</a> class.
in	<i>title</i>	The title of the <a href="#">IpxGenParamTreeView</a> class as a const char.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

## Returns

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



## 6.3.3.2 CreateGenParamTreeViewForArrayW()

```

IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxGenParamTreeView* IpxGui::CreateGenParamTreeViewFor↵
ArrayW (
    IpxGenParam::Array * genParam,
    const wchar_t * title,
    uintptr_t parentWindow = 0 )
  
```

Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object. Unicode version.

This function returns the pointer to the [IpxGenParamTreeView](#) class that was created using information extracted from the [IpxGenParam::Array](#).

## Parameters

in	<i>genParam</i>	The pointer to the <a href="#">IpxGenParam::Array</a> class.
in	<i>title</i>	The title of the <a href="#">IpxGenParamTreeView</a> class as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

**Returns**

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:

**6.3.3.3 CreateGenParamTreeViewForNodemapA()**

```

IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxGenParamTreeView* IpxGui::CreateGenParamTreeViewFor↵
NodemapA (
    IPX_GENAPI_NS::INodeMap * nodemap,
    const char * title,
    uintptr_t parentWindow = 0 )
  
```

Creates the panel of the camera GenICam parameters for GenApi::INodeMap object.

This function returns the pointer to the [IpxGenParamTreeView](#) class that was created using information extracted from the GenApi::INodeMap class.

**Parameters**

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
in	<i>title</i>	The title of the <a href="#">IpxGenParamTreeView</a> class as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

**Returns**

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:

**6.3.3.4 CreateGenParamTreeViewForNodemapW()**

```

IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxGenParamTreeView* IpxGui::CreateGenParamTreeViewFor↵
NodemapW (
    IPX_GENAPI_NS::INodeMap * nodemap,
    const wchar_t * title,
    uintptr_t parentWindow = 0 )
  
```

Creates the panel of the camera GenICam parameters for GenApi::INodeMap object. Unicode version.

This function returns the pointer to the [IpxGenParamTreeView](#) that was created using information extracted from the GenApi::INodeMap class.

**Parameters**

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
in	<i>title</i>	The title of the <a href="#">IpxGenParamTreeView</a> as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

**Returns**

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:

**6.3.3.5 DestroyGenParamTreeView()**

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::DestroyGenParamTreeView (  
    IpxGenParamTreeView * view )
```

Destroys the GenICam parameters panel.

This function closes the camera GenICam parameters panel and destroys the [IpxGenParamTreeView](#) object previously created with `CreateGenParamTreeViewForNodemap*` or `CreateGenParamTreeViewForArray*` function


**Parameters**

in	view	A pointer to the <a href="#">IpxGenParamTreeView</a> class.
----	------	---

**Returns**

void

Here is the caller graph for this function:



### 6.3.3.6 SelectCameraA()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxCam::DeviceInfo* IpxGui::SelectCameraA (
    IpxCam::System * pSystem,
    const char * title,
    uintptr_t parentWindow = 0,
    bool poll = true )
```

Pops-up the camera selection dialog.

This function pops-up the "Select camera" modal dialog, where user can select the Camera and obtain the pointer to [IpxCam::DeviceInfo](#) object for the selected camera


#### Parameters

in	<i>pSystem</i>	The pointer to the <a href="#">IpxCam::System</a> class.
in	<i>title</i>	The title of the selected Camera as a const char variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget
in	<i>poll</i>	Specifies if poll check box should be checked by default, so the System will be polled for new devices to appear

#### Returns

If the function succeeds, the return value is the pointer to the [IpxCam::DeviceInfo](#) class. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



### 6.3.3.7 SelectCameraW()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxCam::DeviceInfo* IpxGui::SelectCameraW (
    IpxCam::System * pSystem,
    const wchar_t * title,
    uintptr_t parentWindow = 0,
    bool poll = true )
```

Pops-up the camera selection dialog. Unicode version.

This function pops-up the "Select camera" modal dialog, where user can select the Camera and obtain the pointer to [IpxCam::DeviceInfo](#) object for the selected camera.


## Parameters

in	<i>pSystem</i>	The pointer to the <a href="#">IpxCam::System</a> class.
in	<i>title</i>	The title of the <a href="#">IpxGenParamTreeView</a> as a <code>wchar_t</code> variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget
in	<i>poll</i>	Specifies if poll check box should be checked by default, so the System will be polled for new devices to appear

## Returns

If the function succeeds, the return value is the pointer to the [IpxCam::DeviceInfo](#) class. Otherwise, the return value is `nullptr`.

Here is the caller graph for this function:



## 6.3.3.8 ShowCamConfigDialog()

```


IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowCamConfigDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
  
```

Show Camera Configuration Dialog.

## Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



#### 6.3.3.9 ShowFrameABDialog()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowFrameABDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
```

##### Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



#### 6.3.3.10 ShowTriggerDialog()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowTriggerDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
```


Show Trigger Dialog.



## Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



## 6.3.3.11 ShowPulseDialog()

```


IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowPulseDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
  
```

Show Pulse Dialog.

## Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



### 6.3.3.12 ShowStrobeDialog()


```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowStrobeDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
```

Show Strobe Dialog.

#### Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



### 6.3.3.13 ShowOutputDialog()

```
IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowOutputDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
```

Show Output Data Dialog.

#### Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



#### 6.3.3.14 ShowColorDialog()

```


IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowColorDialog (
    IpxCam::Device * device,
    uintptr_t parentWindow = 0 )
  
```

Show Color Dialog.

##### Parameters

in	<i>device</i>	The pointer to the <a href="#">IpxCam::Device</a> class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:





## Chapter 7

# Class Documentation

### 7.1 IpxGenParam::Array Class Reference

An [Array](#) class contains methods to access all GenICam camera parameters.

```
#include <IpxCameraApi.h>
```

#### Public Member Functions

- virtual [~Array](#) ()  
*Array class destructor.*
- virtual [Param](#) \* [GetParam](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Param](#) class object for the specified node name from the node map declared in the camera descriptor XML file.*
- virtual [Boolean](#) \* [GetBoolean](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Boolean](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [Command](#) \* [GetCommand](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Command](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [Enum](#) \* [GetEnum](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Enum](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [Float](#) \* [GetFloat](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Float](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [Int](#) \* [GetInt](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [Int](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [String](#) \* [GetString](#) (const char \*name, IpxCamErr \*err)=0  
*This method gets the pointer to the [String](#) class object for the specified node name of the camera descriptor XML file.*
- virtual [Category](#) \* [GetRootCategory](#) (IpxCamErr \*err)=0  
*This method gets the pointer to the root category node object. The Root node is considered a special node. It has no parent node. In the topology graph, it is the top node which connects to at least one child node. The child node may connect to the device node that provides the connection to the transport layer.*
- virtual IPX\_GENAPI\_NS::INodeMap \* [GetNodeMap](#) (IpxCamErr \*err)=0

*This method gets the pointer to the NodeMap interface. The NodeMap interface will provide methods to retrieves all nodes in the node map.*

- virtual uint32\_t [GetCount](#) ()=0

*This method gets the number of nodes.*

- virtual [Param](#) \* [GetParamByIndex](#) (uint32\_t idx, [lpxCamErr](#) \*err)=0

*This method gets the parameter by index.*

- virtual [lpxCamErr](#) [SetBooleanValue](#) (const char \*name, bool aValue)=0

*This method sets the [Boolean](#) value of the [Boolean](#) node.*

- virtual bool [GetBooleanValue](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [Boolean](#) value of the [Boolean](#) node.*

- virtual [lpxCamErr](#) [SetEnumValueStr](#) (const char \*name, const char \*val)=0

*This method sets the [Enum](#) node maps and the [Enum](#) interface to a name and index value. Each of the enum entries are represented by a name and index pair. This method sets the [Enum](#) value [String](#) of the corresponding node. The enum nodes map to a drop down box.*

- virtual [lpxCamErr](#) [SetEnumValue](#) (const char \*name, int64\_t val)=0

*This method sets the [Enum](#) value of the enum node.*

- virtual const char \* [GetEnumValueStr](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [Enum](#) value string of the current set [Enum](#) value entry.*

- virtual int64\_t [GetEnumValue](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [Enum](#) value of the [Enum](#) node.*

- virtual [lpxCamErr](#) [SetFloatValue](#) (const char \*name, double val)=0

*This method sets the [Float](#) value of the [Float](#) node.*

- virtual double [GetFloatValue](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [Float](#) value of the [Float](#) node.*

- virtual [lpxCamErr](#) [SetIntegerValue](#) (const char \*name, int64\_t val)=0

*This method sets the [Integer](#) value of the [Integer](#) node.*

- virtual int64\_t [GetIntegerValue](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [Integer](#) value of the [Integer](#) node.*

- virtual [lpxCamErr](#) [SetStringValue](#) (const char \*name, const char \*val)=0

*This method sets the [String](#) value of the [String](#) node.*

- virtual const char \* [GetStringValue](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method gets the [String](#) value of the [String](#) node.*

- virtual [lpxCamErr](#) [ExecuteCommand](#) (const char \*name)=0

*This method executes/submits the command.*

- virtual bool [IsCommandDone](#) (const char \*name, [lpxCamErr](#) \*err=nullptr)=0

*This method polls the corresponding executed command to see if the executed command is done or not.*

- virtual [lpxCamErr](#) [Poll](#) (int64\_t elapsedTime)=0

*This method fires nodes which have a polling time.*

### 7.1.1 Detailed Description

An [Array](#) class contains methods to access all GenICam camera parameters.

This class contains methods that can access each node from the GenICam camera description XML file by parameters type and name.

## 7.1.2 Constructor & Destructor Documentation

### 7.1.2.1 ~Array()

```
virtual IpxGenParam::Array::~~Array ( ) [inline], [virtual]
```

[Array](#) class destructor.

[Array](#) class destructor. Destroys the [Array](#) object and all its descendants.

## 7.1.3 Member Function Documentation

### 7.1.3.1 GetParam()

```
virtual Param* IpxGenParam::Array::GetParam (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Param](#) class object for the specified node name from the node map declared in the camera descriptor XML file.

#### Parameters

in	<i>name</i>	Unique name of a node in node map.
out	<i>err</i>	Returns an error code: <ul style="list-style-type: none"><li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Param</a> class of the specified node name</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - specified node name not found in camera descriptor XML file</li></ul>

#### Returns

If the method succeeds, it returns the pointer to the [Param](#) class for the specific node name. Otherwise, it returns a nullptr.

### 7.1.3.2 GetBoolean()

```
virtual Boolean* IpxGenParam::Array::GetBoolean (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Boolean](#) class object for the specified node name of the camera descriptor XML file.

#### Parameters

in	<i>name</i>	A unique name of <a href="#">Boolean</a> type node in the camera descriptor XML file.
out	<i>err</i>	Returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Boolean</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>

#### Returns

If the method succeeds, it returns the pointer to the [Boolean](#) class for the specific node name. Otherwise, it returns a nullptr.

### 7.1.3.3 GetCommand()

```
virtual Command* IpxGenParam::Array::GetCommand (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Command](#) class object for the specified node name of the camera descriptor XML file.

#### Parameters

in	<i>name</i>	Unique name of <a href="#">Command</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Command</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>



**Returns**

If method succeeds, it returns the pointer to the [Command](#) class for the specific node name. Otherwise, it returns a nullptr.

**7.1.3.4 GetEnum()**

```
virtual Enum* IpxGenParam::Array::GetEnum (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Enum](#) class object for the specified node name of the camera descriptor XML file.

**Parameters**

in	<i>name</i>	Unique name of Enumeration type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Enum</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>

**Returns**

If the method succeeds, it returns the pointer to the [Enum](#) parameter class for the specific node name. Otherwise, it returns a nullptr.

**7.1.3.5 GetFloat()**

```
virtual Float* IpxGenParam::Array::GetFloat (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Float](#) class object for the specified node name of the camera descriptor XML file.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">Float</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Float</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>
Generated by Doxygen		

**Returns**

If the method succeeds, it returns the pointer to the [Float](#) parameter class for the specific node name

**7.1.3.6 GetInt()**

```
virtual Int* IpxGenParam::Array::GetInt (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [Int](#) class object for the specified node name of the camera descriptor XML file.

**Parameters**

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Int</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>

**Returns**

If the method succeeds, it returns the pointer to the [Int](#) class for the specific node name

**7.1.3.7 GetString()**

```
virtual String* IpxGenParam::Array::GetString (
    const char * name,
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the [String](#) class object for the specified node name of the camera descriptor XML file.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">String</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">String</a> class of the specified node name</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file</li> </ul>

**Returns**

If the method succeeds, it returns the pointer to the [String](#) class for the specific node name

**7.1.3.8 GetRootCategory()**

```
virtual Category* IpxGenParam::Array::GetRootCategory (
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the root category node object. The Root node is considered a special node. It has no parent node. In the topology graph, it is the top node which connects to at least one child node. The child node may connect to the device node that provides the connection to the transport layer.

**Parameters**

out	err	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <a href="#">Category</a> class</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified Root node name not found in camera descriptor XML file</li> </ul>
-----	-----	---

**Returns**

Returns the pointer to the [Category](#) (root node) class

**7.1.3.9 GetNodeMap()**

```
virtual IPX_GENAPI_NS::INodeMap* IpxGenParam::Array::GetNodeMap (
    IpxCamErr * err ) [pure virtual]
```

This method gets the pointer to the NodeMap interface. The NodeMap interface will provide methods to retrieves all nodes in the node map.

**Parameters**

out	err	returns an error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <code>GenApi::INodeMap</code> class</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - the node map does not exist</li> </ul>
-----	-----	---

**Returns**

nodemap returns the pointer to the NodeMap interface

**7.1.3.10 GetCount()**

```
virtual uint32_t IpxGenParam::Array::GetCount ( ) [pure virtual]
```

This method gets the number of nodes.

**Returns**

The number of nodes. This number should be greater than 0.

**7.1.3.11 GetParamByIndex()**

```
virtual Param* IpxGenParam::Array::GetParamByIndex (
    uint32_t idx,
    IpxCamErr * err ) [pure virtual]
```

This method gets the parameter by index.

**Parameters**

in	idx	Index
out	err	returns the error code: <ul style="list-style-type: none"> <li>• IpxCamErr::IPX_CAM_ERR_OK - Successfully returns pointer to <a href="#">Param</a> class</li> <li>• IpxCamErr::IPX_CAM_ERR_INVALID_INDEX - entered invalid index</li> </ul>

**Returns**

Returns param pointer to Parameter class of the specified node referenced by the index value

**7.1.3.12 SetBooleanValue()**

```
virtual IpxCamErr IpxGenParam::Array::SetBooleanValue (
    const char * name,
    bool aValue ) [pure virtual]
```

This method sets the [Boolean](#) value of the [Boolean](#) node.

## Parameters

in	<i>name</i>	Unique name of <a href="#">Boolean</a> node to set
in	<i>aValue</i>	<a href="#">Boolean</a> value to set

## Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully set the [Boolean](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

7.1.3.13 `GetBooleanValue()`

```
virtual bool IpxGenParam::Array::GetBooleanValue (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Boolean](#) value of the [Boolean](#) node.

## Parameters

in	<i>name</i>	Unique name of <a href="#">Boolean</a> node to get
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Boolean</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node</li> </ul>

## Returns

Returns the [Boolean](#) Value

7.1.3.14 `SetEnumValueStr()`

```
virtual IpxCamErr IpxGenParam::Array::SetEnumValueStr (
    const char * name,
    const char * val ) [pure virtual]
```

This method sets the [Enum](#) node maps and the [Enum](#) interface to a name and index value. Each of the enum entries are represented by a name and index pair. This method sets the [Enum](#) value [String](#) of the corresponding node. The enum nodes map to a drop down box.

**Parameters**

in	<i>name</i>	Name of <a href="#">Enum</a> entry node to set
in	<i>val</i>	<a href="#">Enum</a> node string value to set

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Enum](#) Value string
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

**7.1.3.15 SetEnumValue()**

```
virtual IpxCamErr IpxGenParam::Array::SetEnumValue (  
    const char * name,  
    int64_t val ) [pure virtual]
```

This method sets the [Enum](#) value of the enum node.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">Enum</a> entry to set
in	<i>val</i>	<a href="#">Enum</a> entry integer value to set

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully gets the [Enum](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

**7.1.3.16 GetEnumValueStr()**

```
virtual const char* IpxGenParam::Array::GetEnumValueStr (  
    const char * name,  
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Enum](#) value string of the current set [Enum](#) value entry.

## Parameters

in	<i>name</i>	Unique name of <a href="#">Enum</a> entry
out	<i>err</i>	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Enum</a> string value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

## Returns

Get the [Enum](#) value [String](#) of the current set [Enum](#) Value Entry

## 7.1.3.17 GetEnumValue()

```
virtual int64_t IpxGenParam::Array::GetEnumValue (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Enum](#) value of the [Enum](#) node.

## Parameters

in	<i>name</i>	Unique name of <a href="#">Enum</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Enum</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

## Returns

Returns the [Enum](#) Value

## 7.1.3.18 SetFloatValue()

```
virtual IpxCamErr IpxGenParam::Array::SetFloatValue (
    const char * name,
    double val ) [pure virtual]
```

This method sets the [Float](#) value of the [Float](#) node.

#### Parameters

in	<i>name</i>	Unique name of <a href="#">Float</a> type node in the camera descriptor XML file.
in	<i>val</i>	<a href="#">Float</a> value to set

#### Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Float](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

#### 7.1.3.19 GetFloatValue()

```
virtual double IpxGenParam::Array::GetFloatValue (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Float](#) value of the [Float](#) node.

#### Parameters

in	<i>name</i>	Unique name of <a href="#">Float</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Float</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

#### Returns

Returns the [Float](#) value



## 7.1.3.20 SetIntegerValue()

```
virtual IpxCamErr IpxGenParam::Array::SetIntegerValue (
    const char * name,
    int64_t val ) [pure virtual]
```

This method sets the Integer value of the Integer node.

## Parameters

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
in	<i>val</i>	Integer value to set

## Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the Integer value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

## 7.1.3.21 GetIntegerValue()

```
virtual int64_t IpxGenParam::Array::GetIntegerValue (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the Integer value of the Integer node.

## Parameters

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
out	<i>err</i>	<p>returns the error code:</p> <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Integer value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

**Returns**

Returns the Integer value

**7.1.3.22 SetStringValue()**

```
virtual IpxCamErr IpxGenParam::Array::SetStringValue (
    const char * name,
    const char * val ) [pure virtual]
```

This method sets the [String](#) value of the [String](#) node.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">String</a> type node in the camera descriptor XML file.
in	<i>val</i>	<a href="#">String</a> value to set

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [String](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

**7.1.3.23 GetStringValue()**

```
virtual const char* IpxGenParam::Array::GetStringValue (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [String](#) value of the [String](#) node.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">String</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">String</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
		Generated by Doxygen

**Returns**

Returns the [String](#) value

**7.1.3.24 ExecuteCommand()**

```
virtual IpxCamErr IpxGenParam::Array::ExecuteCommand (
    const char * name ) [pure virtual]
```

This method executes/submits the command.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">Command</a> type node in the camera descriptor XML file.
----	-------------	---

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully determines state of executed command.
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

**7.1.3.25 IsCommandDone()**

```
virtual bool IpxGenParam::Array::IsCommandDone (
    const char * name,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method polls the corresponding executed command to see if the executed command is done or not.

**Parameters**

in	<i>name</i>	Unique name of <a href="#">Command</a> type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully determines state of executed command.</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> </ul>

**Returns**

Returns true if the Execute command has finished. Otherwise, returns false.

### 7.1.3.26 Poll()

```
virtual IpxCamErr IpxCamParam::Array::Poll (
    int64_t elapsedTime ) [pure virtual]
```

This method fires nodes which have a polling time.

#### Parameters

in	<i>elapsedTime</i>	Time elapsed since last poll in msec
----	--------------------	--------------------------------------

#### Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully determines state of executed command.
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

## 7.2 IpxCamParam::Boolean Class Reference

A class containing methods for [Boolean](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for `IpxCamParam::Boolean`:



## Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [Boolean](#) type.*
- virtual IpxCamErr [SetValue](#) (bool val)=0  
*This method can be used to set the node value to true or false.*
- virtual bool [GetValue](#) (IpxCamErr \*err=nullptr)=0  
*This method returns the node value. It can return a true or false value.*

### 7.2.1 Detailed Description

A class containing methods for [Boolean](#) GenICam camera parameter.

A class containing methods that map the integer element value of a GenICam IBoolean interface feature to true or false.

For example, the mapping below will illustrate the IBoolean interfaces of a **LUTEnable** feature.

### 7.2.2 Member Function Documentation

#### 7.2.2.1 GetType()

```
virtual ParamType IpxGenParam::Boolean::GetType ( ) [inline], [virtual]
```

This method returns the node object [Boolean](#) type.

#### Returns

Returns the node object [Boolean](#) type

Implements [IpxGenParam::Param](#).

#### 7.2.2.2 SetValue()

```
virtual IpxCamErr IpxGenParam::Boolean::SetValue (
    bool val ) [pure virtual]
```

This method can be used to set the node value to true or false.

**Parameters**

<i>in</i>	<i>val</i>	The node value to set such as true or false
-----------	------------	---

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Boolean](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

**7.2.2.3 GetValue()**

```
virtual bool IpxGenParam::Boolean::GetValue (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method returns the node value. It can return a true or false value.

**Parameters**

<i>out</i>	<i>err</i>	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the value of the <a href="#">Boolean</a> node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
------------	------------	---

**Returns**

The node value read.

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

**7.3 IpxCam::Buffer Class Reference**

The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

## Public Member Functions

- virtual [~Buffer](#) ()  
*Buffer class destructor.*
- virtual `lpxImage *` [GetImage](#) ()=0  
*Returns the pointer to the lpxImage structure.*
- virtual `void *` [GetBufferPtr](#) ()=0  
*Returns the pointer to the image data.*
- virtual `size_t` [GetImageOffset](#) ()=0  
*Returns the offset of the actual image data start.*
- virtual `size_t` [GetBufferSize](#) ()=0  
*This method returns the size of the allocated memory buffer in bytes.*
- virtual `uint64_t` [GetPixelFormat](#) ()=0  
*This method returns the pixel format of the buffer object.*
- virtual `void *` [GetUserPtr](#) ()=0  
*This method returns the user data buffer pointer, associated with the buffer object.*
- virtual `uint64_t` [GetTimestamp](#) ()=0  
*This method returns the timestamp of the acquired buffer.*
- virtual `uint64_t` [GetFrameID](#) ()=0  
*This method returns the identifier of the image stream block of the buffer object.*
- virtual `bool` [IsIncomplete](#) ()=0  
*This method returns a flag indicating if the buffer data has been fully transferred or incompleted.*
- virtual `size_t` [GetWidth](#) ()=0  
*Returns the image width.*
- virtual `size_t` [GetHeight](#) ()=0  
*Returns the image height.*
- virtual `size_t` [GetXOffset](#) ()=0  
*Returns the horizontal offset of the image data in the buffer.*
- virtual `size_t` [GetYOffset](#) ()=0  
*Returns the vertical offset of the image data in the buffer.*
- virtual `size_t` [GetXPadding](#) ()=0  
*This method returns the number of extra bytes padded in the horizontal direction.*
- virtual `size_t` [GetYPadding](#) ()=0  
*This method returns the number of extra bytes padded in the vertical direction.*
- virtual `size_t` [GetDeliveredHeight](#) ()=0  
*This method returns the actual height of delivered data.*
- virtual `bool` [IsKacFrameB](#) ()=0  
*This method indicates if this buffer is Frame A or Frame B, acquired from Cheetah camera with KAC-12040 or KAC-06040 CMOS sensor.*

### 7.3.1 Detailed Description

The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.

The [Buffer](#) class contains the methods that can be used to get the pointer to the acquired image data memory and / or retrieve the information about the received image data such as timestamp, image size, pixel format, etc

### 7.3.2 Constructor & Destructor Documentation

#### 7.3.2.1 ~Buffer()

```
virtual IpxCam::Buffer::~~Buffer ( ) [inline], [virtual]
```

[Buffer](#) class destructor.

Destroys the [Buffer](#) object and all its descendants.

#### Returns

none

### 7.3.3 Member Function Documentation

#### 7.3.3.1 GetImage()

```
virtual IpxImage* IpxCam::Buffer::GetImage ( ) [pure virtual]
```

Returns the pointer to the `IpxImage` structure.

This method returns the pointer to the `IpxImage` structure. See `IpxTools` user's manual for `IpxImage` structure description.

#### Returns

Returns the pointer to the `IpxImage` structure.

#### 7.3.3.2 GetBufferPtr()

```
virtual void* IpxCam::Buffer::GetBufferPtr ( ) [pure virtual]
```

Returns the pointer to the image data.

This method returns the pointer to the memory of the acquired image data.

#### Returns

Returns the pointer to the image data



#### 7.3.3.3 GetImageOffset()

```
virtual size_t IpxCam::Buffer::GetImageOffset ( ) [pure virtual]
```

Returns the offset of the actual image data start.

This method returns the offset of the actual image data start in the acquired data buffer memory.

##### Returns

Returns the offset of the actual image data start

#### 7.3.3.4 GetBufferSize()

```
virtual size_t IpxCam::Buffer::GetBufferSize ( ) [pure virtual]
```

This method returns the size of the allocated memory buffer in bytes.

##### Returns

Returns the buffer size in bytes

#### 7.3.3.5 GetPixelFormat()

```
virtual uint64_t IpxCam::Buffer::GetPixelFormat ( ) [pure virtual]
```

This method returns the pixel format of the buffer object.

##### Returns

Returns the pixel format of the image in the buffer object. This value equals to **PixeFormat** GenICam parameter

#### 7.3.3.6 GetUserPtr()

```
virtual void* IpxCam::Buffer::GetUserPtr ( ) [pure virtual]
```

This method returns the user data buffer pointer, associated with the buffer object.

##### Returns

Returns the user data buffer pointer

#### 7.3.3.7 GetTimestamp()

```
virtual uint64_t IpxCam::Buffer::GetTimestamp ( ) [pure virtual]
```

This method returns the timestamp of the acquired buffer.

This method returns the timestamp of the acquired buffer. Imperx USB3 and GEV cameras have 10ns timestamp granularity. GEV cameras timestamp clock frequency can be obtained from **GevTimestampTickFrequency** GenICam parameter

##### Returns

Returns the timestamp of the acquired buffer.

#### 7.3.3.8 GetFrameID()

```
virtual uint64_t IpxCam::Buffer::GetFrameID ( ) [pure virtual]
```

This method returns the identifier of the image stream block of the buffer object.

##### Returns

Returns the identifier of the image stream block of the buffer object.

#### 7.3.3.9 IsIncomplete()

```
virtual bool IpxCam::Buffer::IsIncomplete ( ) [pure virtual]
```

This method returns a flag indicating if the buffer data has been fully transferred or incompleted.

##### Returns

Returns True, if buffer transfer was incompleted, False, if transfer was successful

#### 7.3.3.10 GetWidth()

```
virtual size_t IpxCam::Buffer::GetWidth ( ) [pure virtual]
```

Returns the image width.

This method returns the image width of the buffer data in number of pixels. Usually the return value equals to **Width** GenICam parameter value

##### Returns

Returns the image width

#### 7.3.3.11 GetHeight()

```
virtual size_t IpxCam::Buffer::GetHeight ( ) [pure virtual]
```

Returns the image height.

This method returns the image height of the buffer data in number of lines. Usually the return value equals to **Height** GenICam parameter value

##### Returns

Returns the image height

#### 7.3.3.12 GetXOffset()

```
virtual size_t IpxCam::Buffer::GetXOffset ( ) [pure virtual]
```

Returns the horizontal offset of the image data in the buffer.

This method returns the horizontal offset of the image data in the buffer in number of pixels from the image origin. Usually the return value equals to **OffsetX** GenICam parameter value

##### Returns

Returns the horizontal offset in number of pixels

#### 7.3.3.13 GetYOffset()

```
virtual size_t IpxCam::Buffer::GetYOffset ( ) [pure virtual]
```

Returns the vertical offset of the image data in the buffer.

This method returns the vertical offset of the image data in the buffer in number of lines from the image origin. Usually the return value equals to **OffsetY** GenICam parameter value

##### Returns

Returns the vertical offset of the data in the buffer in number of lines from the image origin

#### 7.3.3.14 GetXPadding()

```
virtual size_t IpxCam::Buffer::GetXPadding ( ) [pure virtual]
```

This method returns the number of extra bytes padded in the horizontal direction.

##### Returns

Returns the XPadding of the data in the buffer in number of bytes

#### 7.3.3.15 GetYPadding()

```
virtual size_t IpxCam::Buffer::GetYPadding ( ) [pure virtual]
```

This method returns the number of extra bytes padded in the vertical direction.

##### Returns

Returns the YPadding of the data in the buffer in number of bytes

#### 7.3.3.16 GetDeliveredHeight()

```
virtual size_t IpxCam::Buffer::GetDeliveredHeight ( ) [pure virtual]
```

This method returns the actual height of delivered data.

This method returns the actual height of delivered data. Can be different than value returned by [GetHeight\(\)](#) method, if image transfer was incompleted.

##### Returns

Returns the actual height of delivered data

## 7.3.3.17 IsKacFrameB()

```
virtual bool IpxCam::Buffer::IsKacFrameB ( ) [pure virtual]
```

This method indicates if this buffer is Frame A or Frame B, acquired from Cheetah camera with KAC-12040 or KAC-06040 CMOS sensor.

## Returns

Returns true for Frame B, false - otherwise

The documentation for this class was generated from the following file:


- IpxCameraApi.h

## 7.4 IpxGenParam::Category Class Reference

A class containing methods for GenlCam [Category](#).

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Category:



## Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [Category](#) type.*
- virtual uint32\_t [GetCount](#) ()=0  
*This method returns the number of parameters in the category.*
- virtual [Param](#) \* [GetParamByIndex](#) (uint32\_t idx, IpxCamErr \*err)=0  
*This method returns the Parameter by Index.*

### 7.4.1 Detailed Description

A class containing methods for GenICam [Category](#).

A class containing methods that the user can access the categories of GenICam features. It will access the node object's of an ICategory interface. Each feature of a device will be placed in a [Category](#). The [Category](#) feature is used to present the user with a group of features for the named category.

For example, the mapping below will illustrate the ICategory interfaces categories such as DeviceControl and Event↔Control.

### 7.4.2 Member Function Documentation

#### 7.4.2.1 GetType()

```
virtual ParamType IpxGenParam::Category::GetType ( ) [inline], [virtual]
```

This method returns the node object [Category](#) type.

##### Returns

Returns the node object [Category](#) type

Implements [IpxGenParam::Param](#).

#### 7.4.2.2 GetCount()

```
virtual uint32_t IpxGenParam::Category::GetCount ( ) [pure virtual]
```

This method returns the number of parameters in the category.

##### Returns

Returns the number of parameters in the category

#### 7.4.2.3 GetParamByIndex()

```
virtual Param\* IpxGenParam::Category::GetParamByIndex (
    uint32_t idx,
    IpxCamErr * err ) [pure virtual]
```

This method returns the Parameter by Index.

## Parameters

in	idx	index
out	err	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to the parameter for specified index</li> <li>• <code>IpxCamErr::IPX_CAM_ERR_INVALID_INDEX</code> - an invalid index for node</li> </ul>

## Returns

Returns the pointer to the parameter object

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

## 7.5 IpxGenParam::Command Class Reference

A class containing methods for [Command](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for `IpxGenParam::Command`:



## Public Member Functions

- virtual [ParamType](#) `GetType` ()  
*This method returns the node object [Command](#) type.*
- virtual `IpxCamErr` [Execute](#) ()=0  
*This method executes the command.*
- virtual bool [IsDone](#) (`IpxCamErr *err=nullptr`)=0  
*This method queries whether the command is executed and completed.*

### 7.5.1 Detailed Description

A class containing methods for [Command](#) GenICam camera parameter.

A class for GenICam [Command](#) contains methods that allow the user submit a command for execution as well as poll the command status.

For example, the mapping below will illustrate the ICommand interface for AcquisitionStart. This feature starts the Acquisition of the device.

### 7.5.2 Member Function Documentation

#### 7.5.2.1 GetType()

```
virtual ParamType IpxGenParam::Command::GetType ( ) [inline], [virtual]
```

This method returns the node object [Command](#) type.

##### Returns

Returns the node object [Command](#) type

Implements [IpxGenParam::Param](#).

#### 7.5.2.2 Execute()

```
virtual IpxCamErr IpxGenParam::Command::Execute ( ) [pure virtual]
```

This method executes the command.

##### Returns

the error code

#### 7.5.2.3 IsDone()

```
virtual bool IpxGenParam::Command::IsDone (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method queries whether the command is executed and completed.



## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully determined that state of execute command</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TREE_ERROR</code> - Unable to access tree</li> </ul>
-----	-----	--

## Returns

If set to TRUE, the Execute command has finished. Otherwise, it returns FALSE.

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

## 7.6 IpxCam::Device Class Reference

The [Device](#) class represents the device module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

## Public Types

- enum [UploadEventType](#) : `uint32_t` { [FlashSectorErase](#), [FlashPageWrite](#), [FlashPageRead](#) }
  - enum [Endianness](#) : `uint8_t` { [BigEndian](#), [LittleEndian](#) }
- An enum of endianness types of underlying protocol.*

## Public Member Functions

- virtual [~Device](#) ()  
*A destructor of the [Device](#) class.*
- virtual void [Release](#) ()=0  
*This method releases the instance of the device object. This method releases the device object.*
- virtual `uint32_t` [GetNumStreams](#) ()=0  
*This method retrieves the number of the data streams, provided by the [Device](#).*
- virtual [Stream](#) \* [GetStreamByIndex](#) (`uint32_t` idx=0)=0  
*This retrieves the pointer to the [Stream](#) object by stream index.*
- virtual [Stream](#) \* [GetStreamById](#) (`const char` \*id)=0  
*This method retrieves the pointer to the [Stream](#) object by stream identifier.*
- virtual [DeviceInfo](#) \* [GetInfo](#) ()=0  
*This method returns a pointer to the [DeviceInfo](#) object , associated with the [Device](#).*

- virtual `lpxCamErr ReadMem` (`uint64_t addr`, `void *data`, `size_t len`)=0  
*This method reads a number of bytes from a given address of the [Device](#).*
- virtual `lpxCamErr WriteMem` (`uint64_t addr`, `const void *data`, `size_t len`, `size_t *written`)=0  
*This method writes a number of bytes at a given address.*
- virtual `lpxCamErr RegisterEvent2` (`uint32_t eventType`, `lpxCam::EventCallback2 *eventCallback`, `void *p←Private`)=0  
*This method registers the [Device](#) class method as a callback method to be called when a `eventType` occurs.*
- virtual `lpxCamErr RegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *pPrivate`)=0  
*RegisterEvent.*
- virtual `lpxCamErr UnRegisterEvent2` (`uint32_t eventType`, `lpxCam::EventCallback2 *eventCallback`, `void *p←Private`)=0  
*This event occurs, when the camera was disconnected from the [System](#).*
- virtual `lpxCamErr UnRegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *p←Private`)=0  
*UnRegisterEvent.*
- virtual `lpxGenParam::Array * GetTransportParameters` (`lpxCamErr *err=nullptr`)=0  
*This method returns the transport parameters [lpxGenParam::Array](#) object of the camera device object.*
- virtual `lpxGenParam::Array * GetCameraParameters` (`lpxCamErr *err=nullptr`)=0  
*This method returns the camera parameters [lpxGenParam::Array](#) object of the device object.*
- virtual `lpxCamErr SaveConfiguration` (`const char *fileName`)=0  
*This method saves the camera parameters to the configuration file.*
- virtual `lpxCamErr LoadConfiguration` (`const char *fileName`)=0  
*This method loads the configuration from file, and configures the camera with the parameter values, saved to this file.*
- virtual `Endianness GetEndianness` () `const` =0  
*This method returns endianness of underlying protocol for this camera device.*

## Static Public Attributes

- static const `uint32_t CameraConnected` = 1003  
*This event occurs, if [GenICam](#) event was triggered by the camera device.*
- static const `uint32_t CameraDisconnected` = 1004  
*This event occurs, when the camera was connected to the [System](#).*

## 7.6.1 Detailed Description

The [Device](#) class represents the device module in the GenTL module hierarchy.

This [Device](#) class provides methods to enable the communication and control of the Imperx device and enumerate/instantiate data stream objects. The methods can be used to enumerate and instantiate the Data [Stream](#) module objects. The device must correspond to the interface transport layer technology. For example, the device could be an Imperx GEV Camera and the transport layer technology would be GEV. The [Device](#) class can be used to retrieve data information about the device by returning the pointer to the [DeviceInfo](#) class. It can be used to retrieve the pointer to the [Stream](#) object and save / load the camera configurations to / from file.

## 7.6.2 Member Enumeration Documentation

### 7.6.2.1 UploadEventType

```
enum IpxCam::Device::UploadEventType : uint32_t
```

### Enumerator

FlashSectorErase	Enum value FlashSectorErase.
FlashPageWrite	Enum value FlashPagewrite.
FlashPageRead	Enum value FlashPageRead.

### 7.6.2.2 Endianness

```
enum IpxCam::Device::Endianness : uint8_t
```

An enum of endianness types of underlying protocol.

### Enumerator

BigEndian	Enum value Big-endian.
LittleEndian	Enum value Little-endian

## 7.6.3 Constructor & Destructor Documentation

### 7.6.3.1 ~Device()

```
virtual IpxCam::Device::~~Device ( ) [inline], [virtual]
```

A destructor of the [Device](#) class.

Destructor. Destroys the [Device](#) and all its descendants.

## 7.6.4 Member Function Documentation

### 7.6.4.1 GetNumStreams()

```
virtual uint32_t IpxCam::Device::GetNumStreams ( ) [pure virtual]
```

This method retrieves the number of the data streams, provided by the [Device](#).

### Returns

returns the number of the data streams

#### 7.6.4.2 GetStreamByIndex()

```
virtual Stream* IpxCam::Device::GetStreamByIndex (
    uint32_t idx = 0 ) [pure virtual]
```

This retrieves the pointer to the [Stream](#) object by stream index.

##### Parameters

in	<i>idx</i>	stream index value
----	------------	--------------------

##### Returns

Returns the pointer to the [Stream](#) object

#### 7.6.4.3 GetStreamById()

```
virtual Stream* IpxCam::Device::GetStreamById (
    const char * id ) [pure virtual]
```

This method retrieves the pointer to the [Stream](#) object by stream identifier.

##### Parameters

in	<i>id</i>	pointer to the string representing the stream identifier
----	-----------	--

##### Returns

Returns the pointer to the [Stream](#) object

#### 7.6.4.4 GetInfo()

```
virtual DeviceInfo* IpxCam::Device::GetInfo ( ) [pure virtual]
```

This method returns a pointer to the [DeviceInfo](#) object , associated with the [Device](#).

##### Returns

Returns the pointer to the [DeviceInfo](#) object

#### 7.6.4.5 ReadMem()

```
virtual IpxCamErr IpxCam::Device::ReadMem (
    uint64_t addr,
    void * data,
    size_t len ) [pure virtual]
```

This method reads a number of bytes from a given address of the [Device](#).

##### Parameters

in	<i>addr</i>	Byte address to read from
in	<i>data</i>	pointer to a user allocated byte data buffer
in	<i>len</i>	size of the amount of bytes to read from the register map address

##### Returns

Returns ErrorCode

#### 7.6.4.6 WriteMem()

```
virtual IpxCamErr IpxCam::Device::WriteMem (
    uint64_t addr,
    const void * data,
    size_t len,
    size_t * written ) [pure virtual]
```

This method writes a number of bytes at a given address.

##### Parameters

in	<i>addr</i>	Byte address to read from
in	<i>data</i>	pointer to a user allocated byte data buffer
in	<i>len</i>	size of the amount of bytes to write to the register map address
out	<i>written</i>	size of bytes written

##### Returns

Returns ErrorCode

## 7.6.4.7 RegisterEvent2()

```
virtual IpxCamErr IpxCam::Device::RegisterEvent2 (
    uint32_t eventType,
    IpxCam::EventCallback2 * eventCallback,
    void * pPrivate ) [pure virtual]
```

This method registers the [Device](#) class method as a callback method to be called when a eventType occurs.

## Parameters

in	<i>eventType</i>	Event Type, can receive one of the following values: <ul style="list-style-type: none"> <li>• <b>GenICamEvent</b> [1002] - this event occurs, if GenICam event was triggered by the camera</li> <li>• <b>CameraConnected</b> [1003] - this event occurs, when camera was connected to the <a href="#">System</a></li> <li>• <b>CameraDisconnected</b> [1004] - this event occurs, when camera was disconnected from the <a href="#">System</a></li> </ul>
in	<i>eventCallback</i>	event CallBack
in	<i>pPrivate</i>	pointer to user's data

## Returns

Returns Error code

## 7.6.4.8 RegisterEvent()

```
virtual IpxCamErr IpxCam::Device::RegisterEvent (
    uint32_t eventType,
    IpxCam::EventCallback * eventCallback,
    void * pPrivate ) [pure virtual]
```

RegisterEvent.

**Deprecated** Use [Device::RegisterEvent2](#) instead

## 7.6.4.9 UnRegisterEvent2()

```
virtual IpxCamErr IpxCam::Device::UnRegisterEvent2 (
    uint32_t eventType,
    IpxCam::EventCallback2 * eventCallback,
    void * pPrivate ) [pure virtual]
```

This event occurs, when the camera was disconnected from the [System](#).

This method unregisters the [Interface](#) class callback method for the eventType.

## Parameters

in	<i>eventType</i>	Event Type, can receive one of the following values: <ul style="list-style-type: none"> <li>• <b>GenICamEvent</b> [1002] - this event occurs, if GenICam event was triggered by the camera</li> <li>• <b>CameraConnected</b> [1003] - this event occurs, when camera was connected to the <a href="#">System</a></li> <li>• <b>CameraDisconnected</b> [1004] - this event occurs, when camera was disconnected from the <a href="#">System</a></li> </ul>
in	<i>eventCallback</i>	event CallBack
in	<i>pPrivate</i>	pointer to user's data

## Returns

Returns Error code

## 7.6.4.10 UnRegisterEvent()

```
virtual IpxCamErr IpxCam::Device::UnRegisterEvent (
    uint32_t eventType,
    IpxCam::EventCallback * eventCallback,
    void * pPrivate ) [pure virtual]
```

UnRegisterEvent.

**Deprecated** Use [Device::UnRegisterEvent2](#) instead

## 7.6.4.11 GetTransportParameters()

```
virtual IpxGenParam::Array* IpxCam::Device::GetTransportParameters (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method returns the transport parameters [IpxGenParam::Array](#) object of the camera device object.

## Parameters

out	<i>err</i>	returns error code
-----	------------	--------------------



**Returns**

Returns the Transport parameters object pointer

**7.6.4.12 GetCameraParameters()**

```
virtual IpxGenParam::Array* IpxCam::Device::GetCameraParameters (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method returns the camera parameters [IpxGenParam::Array](#) object of the device object.

**Parameters**

out	<i>err</i>	returns error code
-----	------------	--------------------

**Returns**

Returns the Camera Parameters array object pointer

**7.6.4.13 SaveConfiguration()**

```
virtual IpxCamErr IpxCam::Device::SaveConfiguration (
    const char * fileName ) [pure virtual]
```

This method saves the camera parameters to the configuration file.

**Parameters**

in	<i>fileName</i>	Configuration file name
----	-----------------	-------------------------

**Returns**

Returns Error code

**7.6.4.14 LoadConfiguration()**

```
virtual IpxCamErr IpxCam::Device::LoadConfiguration (
    const char * fileName ) [pure virtual]
```

This method loads the configuration from file, and configures the camera with the parameter values, saved to this file.

**Parameters**

in	<i>fileName</i>	Configuration file name
----	-----------------	-------------------------

**Returns**

Returns Error code

**7.6.4.15 GetEndianness()**

```
virtual Endianness IpxCam::Device::GetEndianness ( ) const [pure virtual]
```

This method returns endianness of underlying protocol for this camera device.

**Returns**

Returns endianness

The documentation for this class was generated from the following file:

- IpxCameraApi.h

**7.7 IpxCam::DeviceInfo Class Reference**

[DeviceInfo](#) class provides the information about the camera device.

```
#include <IpxCameraApi.h>
```

**Public Member Functions**

- virtual [~DeviceInfo](#) ()  
*DeviceInfo class destructor.*
- virtual [Interface](#) \* [GetInterface](#) ()=0  
*This method returns the interface of the device object.*
- virtual const char \* [GetID](#) ()=0  
*This method returns the unique device identifier string for the Imperx Camera device object.*
- virtual const char \* [GetVendor](#) ()=0  
*This method returns the vendor name of the camera device object.*
- virtual const char \* [GetModel](#) ()=0  
*This method returns the model name of the camera device object.*
- virtual const char \* [GetDisplayName](#) ()=0

- This method returns the user readable display name of the Camera device object.*
- virtual const char \* [GetUserDefinedName](#) ()=0  
*This method returns the user defined name of the Camera device.*
- virtual const char \* [GetSerialNumber](#) ()=0  
*This method returns the serial number of the Camera device .*
- virtual const char \* [GetVersion](#) ()=0  
*This method returns the device version of the device object.*
- virtual int32\_t [GetAccessStatus](#) ()=0  
*Returns the device access status.*
- virtual const char \* [GetUSB3HostInfo](#) ()=0  
*Returns the information about USB3 host controller.*
- virtual const char \* [GetIPAddress](#) (IpxCamErr \*err)=0  
*Returns the IP address of the GEV camera.*
- virtual const char \* [GetIPMask](#) (IpxCamErr \*err)=0  
*Returns the IP subnet mask of the GEV camera.*
- virtual const char \* [GetIPGateway](#) (IpxCamErr \*err)=0  
*Returns the IP gateway of GEV camera.*
- virtual IpxCamErr [GetIP](#) (uint32\_t \*addr, uint32\_t \*netmask, uint32\_t \*gateway)=0  
*Gets IP information from the GEV camera.*
- virtual IpxCamErr [ForceIP](#) (const char \*addr, const char \*netmask, const char \*gateway)=0  
*Set the IP address to GEV camera.*
- virtual IpxCamErr [ForceIP](#) (uint32\_t addr, uint32\_t netmask, uint32\_t gateway)=0  
*Set IP address to GEV camera.*

### 7.7.1 Detailed Description

[DeviceInfo](#) class provides the information about the camera device.

The [DeviceInfo](#) class can be used to retrieve the information about the device, and to create the [IpxCam::Device](#) object by `IpxCam_CreateDevice()` call

### 7.7.2 Constructor & Destructor Documentation

#### 7.7.2.1 ~DeviceInfo()

```
virtual IpxCam::DeviceInfo::~DeviceInfo ( ) [inline], [virtual]
```

[DeviceInfo](#) class destructor.

Destroys the [DeviceInfo](#) object and all its descendants.

### 7.7.3 Member Function Documentation

#### 7.7.3.1 GetInterface()

```
virtual Interface* IpxCam::DeviceInfo::GetInterface ( ) [pure virtual]
```

This method returns the interface of the device object.

Returns the [IpxCam::Interface](#) object pointer for the camera device, associated with the [DeviceInfo](#) object

##### Returns

Returns the [Interface](#)

#### 7.7.3.2 GetID()

```
virtual const char* IpxCam::DeviceInfo::GetID ( ) [pure virtual]
```

This method returns the unique device identifier string for the Imperx Camera device object.

##### Returns

Returns the unique device identifier string for the Imperx Camera device

#### 7.7.3.3 GetVendor()

```
virtual const char* IpxCam::DeviceInfo::GetVendor ( ) [pure virtual]
```

This method returns the vendor name of the camera device object.

##### Returns

Returns the camera device vendor name

#### 7.7.3.4 GetModel()

```
virtual const char* IpxCam::DeviceInfo::GetModel ( ) [pure virtual]
```

This method returns the model name of the camera device object.

##### Returns

Returns the Camera device model name

#### 7.7.3.5 GetDisplayName()

```
virtual const char* IpxCam::DeviceInfo::GetDisplayName ( ) [pure virtual]
```

This method returns the user readable display name of the Camera device object.

##### Returns

Returns the name of the Camera device

#### 7.7.3.6 GetUserDefinedName()

```
virtual const char* IpxCam::DeviceInfo::GetUserDefinedName ( ) [pure virtual]
```

This method returns the user defined name of the Camera device.

##### Returns

Returns the user defined name of the Camera device

#### 7.7.3.7 GetSerialNumber()

```
virtual const char* IpxCam::DeviceInfo::GetSerialNumber ( ) [pure virtual]
```

This method returns the serial number of the Camera device .

##### Returns

Returns the serial number of the Camera device

#### 7.7.3.8 GetVersion()

```
virtual const char* IpxCam::DeviceInfo::GetVersion ( ) [pure virtual]
```

This method returns the device version of the device object.

##### Returns

Returns the [Device](#) version

#### 7.7.3.9 GetAccessStatus()

```
virtual int32_t IpxCam::DeviceInfo::GetAccessStatus ( ) [pure virtual]
```

Returns the device access status.

This method returns the information about the current access status of the Camera device

##### Returns

Status Access Code, can receive one of the following values:

- **AccessStatusUnknown** [0] - The current availability of the device is unknown.
- **AccessStatusReadWrite** [1] - The device is available for Read/Write access
- **AccessStatusReadOnly** [2] - The device is available for Read only access
- **AccessStatusNoAccess** [3] - The device is not available either because it is already open or because it is not reachable.
- **IpSubnetMismatch** [1001] - The device is available, but IP address does not match to the host subnet mask.

#### 7.7.3.10 GetUSB3HostInfo()

```
virtual const char* IpxCam::DeviceInfo::GetUSB3HostInfo ( ) [pure virtual]
```

Returns the information about USB3 host controller.

This method returns the information about USB3 host controller where the camera device is connected to.

##### Returns

Returns the pointer to string structure or nullptr for non-USB camera

#### 7.7.3.11 GetIPAddress()

```
virtual const char* IpxCam::DeviceInfo::GetIPAddress (
    IpxCamErr * err ) [pure virtual]
```

Returns the IP address of the GEV camera.

This method returns the IP address of the GEV camera, retrieved from DISCOVERY\_ACK packet, received from the camera device

**Parameters**

out	err	Error code
-----	-----	------------

**Returns**

Returns IP Address string or nullptr for non-GEV camera

**7.7.3.12 GetIPMask()**

```
virtual const char* IpxCam::DeviceInfo::GetIPMask (  
    IpxCamErr * err ) [pure virtual]
```

Returns the IP subnet mask of the GEV camera.

This method returns the IP subnet mask of the GEV camera, retrieved from DISCOVERY\_ACK packet, received from the camera device

**Parameters**

out	err	Error code
-----	-----	------------

**Returns**

Returns IP subnet mask string or nullptr for non-GEV camera

**7.7.3.13 GetIPGateway()**

```
virtual const char* IpxCam::DeviceInfo::GetIPGateway (  
    IpxCamErr * err ) [pure virtual]
```

Returns the IP gateway of GEV camera.

This method returns the IP gateway of the GEV camera, retrieved from DISCOVERY\_ACK packet, received from the camera device

**Parameters**

out	err	Error code
-----	-----	------------

**Returns**

Returns IP gateway string or nullptr for non-GEV camera

**7.7.3.14 GetIP()**

```
virtual IpxCamErr IpxCam::DeviceInfo::GetIP (
    uint32_t * addr,
    uint32_t * netmask,
    uint32_t * gateway ) [pure virtual]
```

Gets IP information from the GEV camera.

This method returns the IP address, netmask, and gateway of the GEV camera, from DISCOVERY\_ACK packet, received from the camera

**Parameters**

out	<i>addr</i>	IP Address
out	<i>netmask</i>	IP Address subnet mask
out	<i>gateway</i>	Gateway address

**Returns**

Returns Error code

**7.7.3.15 ForceIP()** [1/2]

```
virtual IpxCamErr IpxCam::DeviceInfo::ForceIP (
    const char * addr,
    const char * netmask,
    const char * gateway ) [pure virtual]
```

Set the IP address to GEV camera.

This method sets the specified IP address to the GEV camera, using ForceIP GVCP command

**Parameters**

in	<i>addr</i>	IP Address string to set
in	<i>netmask</i>	IP Address subnet mask string
in	<i>gateway</i>	Gateway address string



**Returns**

Returns Error code

**7.7.3.16 ForceIP()** [2/2]

```
virtual IpxCamErr IpxCam::DeviceInfo::ForceIP (
    uint32_t addr,
    uint32_t netmask,
    uint32_t gateway ) [pure virtual]
```

Set IP address to GEV camera.

This method sets the specified IP address to the GEV camera, using ForceIP GVCP command

**Parameters**

in	<i>addr</i>	IP Address to set (host byte order)
in	<i>netmask</i>	IP Address subnet mask (host byte order)
in	<i>gateway</i>	Gateway address (host byte order)

**Returns**

Returns Error code

The documentation for this class was generated from the following file:


- IpxCameraApi.h

## 7.8 IpxGenParam::Enum Class Reference

A class containing methods for Enumeration GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Enum:



## Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [Enum](#) type.*
- virtual [size\\_t](#) [GetEnumEntriesCount](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the number of entry nodes.*
- virtual [EnumEntry](#) \* [GetEnumEntryByIndex](#) (size\_t aIndex)=0  
*This method gets the [Enum](#) Entry node by the Index number.*
- virtual [EnumEntry](#) \* [GetEnumEntryByName](#) (const char \*name)=0  
*This method gets the [Enum](#) Entry node by Name.*
- virtual [EnumEntry](#) \* [GetEnumEntryByValue](#) (int64\_t val)=0  
*This method gets the [Enum](#) Entry node by Value.*
- virtual [int64\\_t](#) [GetValue](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the [Enum](#) Entry node value as Integer.*
- virtual const char \* [GetValueStr](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the [Enum](#) Entry node value as [String](#).*
- virtual IpxCamErr [SetValue](#) (int64\_t val)=0  
*This method sets the [Enum](#) Entry node value as Integer.*
- virtual IpxCamErr [SetValueStr](#) (const char \*val)=0  
*This method sets the [Enum](#) Entry node as [String](#).*

### 7.8.1 Detailed Description

A class containing methods for Enumeration GenICam camera parameter.

A class containing methods to access the Enumeration GenICam camera parameter, using Integer or [String](#) value.

For example, the picture below illustrates the enumeration "WhiteBalanceMode".

## 7.8.2 Member Function Documentation

### 7.8.2.1 GetType()

```
virtual ParamType IpxGenParam::Enum::GetType ( ) [inline], [virtual]
```

This method returns the node object [Enum](#) type.

#### Returns

If the method succeeds, it will returns the [Enum](#) parameter type.

Implements [IpxGenParam::Param](#).

### 7.8.2.2 GetEnumEntriesCount()

```
virtual size_t IpxGenParam::Enum::GetEnumEntriesCount (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the number of entry nodes.

#### Parameters

out	err	returns error code:
		<ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the number of EnumEntries</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

#### Returns

Returns the number of enum entry nodes.

### 7.8.2.3 GetEnumEntryByIndex()

```
virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByIndex (
    size_t aIndex ) [pure virtual]
```

This method gets the [Enum](#) Entry node by the Index number.

**Parameters**

in	<i>aIndex</i>	Index number
----	---------------	--------------

**Returns**

If the method succeeds, it returns the [Enum](#) Entry node.

**7.8.2.4 GetEnumEntryByName()**

```
virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByName (
    const char * name ) [pure virtual]
```

This method gets the [Enum](#) Entry node by Name.

**Parameters**

in	<i>name</i>	Entry Name
----	-------------	------------

**Returns**

If the method succeeds, it returns the [Enum](#) Entry node.

**7.8.2.5 GetEnumEntryByValue()**

```
virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByValue (
    int64_t val ) [pure virtual]
```

This method gets the [Enum](#) Entry node by Value.

**Parameters**

in	<i>val</i>	Entry Value
----	------------	-------------

**Returns**

If the method succeeds, it returns the [Enum](#) Entry node.

### 7.8.2.6 GetValue()

```
virtual int64_t IpxGenParam::Enum::GetValue (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Enum](#) Entry node value as Integer.

#### Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Enum</a> Entry node value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

#### Returns

If the method succeeds, it returns the [Enum](#) Entry node value.

### 7.8.2.7 GetValueStr()

```
virtual const char* IpxGenParam::Enum::GetValueStr (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Enum](#) Entry node value as [String](#).

#### Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully get the <a href="#">Enum</a> Entry node string</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

#### Returns

If the method succeeds, it returns the [Enum](#) Entry node string.

#### 7.8.2.8 SetValue()

```
virtual IpxCamErr IpxGenParam::Enum::SetValue (
    int64_t val ) [pure virtual]
```

This method sets the [Enum](#) Entry node value as Integer.

##### Parameters

in	val	<a href="#">Enum</a> Entry node value
----	-----	---------------------------------------

##### Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Enum](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type

#### 7.8.2.9 SetValueStr()

```
virtual IpxCamErr IpxGenParam::Enum::SetValueStr (
    const char * val ) [pure virtual]
```

This method sets the [Enum](#) Entry node as [String](#).

##### Parameters

in	val	<a href="#">Enum</a> Entry node <a href="#">String</a>
----	-----	--

##### Returns

Returns the error code

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

## 7.9 IpxGenParam::EnumEntry Class Reference

[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::EnumEntry:



## Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [EnumEntry](#) type.*
- virtual int64\_t [GetValue](#) (IpxCamErr \*err=NULLPTR)=0  
*This method gets the [EnumEntry](#) numerical value.*
- virtual const char \* [GetValueStr](#) (IpxCamErr \*err=NULLPTR)=0  
*This method gets the [EnumEntry String](#) value.*

### 7.9.1 Detailed Description

[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.

A Class for GenICam [Enum](#) Entries has methods to access the Enumeration GenICam parameter entry.

For example, the mapping below illustrates entries of the IEnumeration interface for the AOI2\_Select feature. This feature can select the mode of operation for Slave AOI #2. The enumeration entries could be "Off", "Include", and "Exclude".

### 7.9.2 Member Function Documentation



### 7.9.2.1 GetType()

```
virtual ParamType IpxGenParam::EnumEntry::GetType ( ) [inline], [virtual]
```

This method returns the node object [EnumEntry](#) type.

#### Returns

If the method succeeds, it returns the ParamType object type of the [EnumEntry](#).

Implements [IpxGenParam::Param](#).

### 7.9.2.2 GetValue()

```
virtual int64_t IpxGenParam::EnumEntry::GetValue (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [EnumEntry](#) numerical value.

#### Parameters

out	err	returns error code:
		<ul style="list-style-type: none"><li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully indicates <a href="#">EnumEntry</a> value was retrieved</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li></ul>

#### Returns

If the method succeeds, it returns the value read of the [EnumEntry](#).

### 7.9.2.3 GetValueStr()

```
virtual const char* IpxGenParam::EnumEntry::GetValueStr (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [EnumEntry String](#) value.

### Parameters

out	err	returns error code: <ul style="list-style-type: none"><li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully indicates <a href="#">EnumEntry</a> string value was retrieved</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li></ul>
-----	-----	---

### Returns

If the method succeeds, it returns the [String](#) value read of the [EnumEntry](#).

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

## 7.10 IpxGenParam::Float Class Reference

A class containing methods for [Float](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for `IpxGenParam::Float`:



## Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [Float](#) type.*
- virtual IpxCamErr [SetValue](#) (double val)=0  
*This method sets the node value.*
- virtual double [GetValue](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the [Float](#) node value.*
- virtual double [GetMin](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the minimum value.*
- virtual double [GetMax](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the maximum value.*
- virtual const char \* [GetUnit](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the Unit.*

### 7.10.1 Detailed Description

A class containing methods for [Float](#) GenICam camera parameter.

A class containing methods to access the [Float](#) GenICam camera parameter as floating point value.

For example, the picture below illustrates the float "ExposureTime".

### 7.10.2 Member Function Documentation

#### 7.10.2.1 GetType()

```
virtual ParamType IpxGenParam::Float::GetType ( ) [inline], [virtual]
```

This method returns the node object [Float](#) type.

#### Returns

Returns the parameter type

Implements [IpxGenParam::Param](#).

#### 7.10.2.2 SetValue()

```
virtual IpxCamErr IpxGenParam::Float::SetValue (  
    double val ) [pure virtual]
```

This method sets the node value.

**Parameters**

in	val	The value to set
----	-----	------------------

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Float](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

**7.10.2.3 GetValue()**

```
virtual double IpxGenParam::Float::GetValue (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Float](#) node value.

**Parameters**

out	err	returns error code:
		<ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully get the <a href="#">Float</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

**Returns**

Gets the [Float](#) node value

**7.10.2.4 GetMin()**

```
virtual double IpxGenParam::Float::GetMin (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the minimum value.

## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Minimum float value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

## Returns

Returns the minimum

## 7.10.2.5 GetMax()

```
virtual double IpxGenParam::Float::GetMax (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the maximum value.

## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Maximum float value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

## Returns

Returns the maximum

## 7.10.2.6 GetUnit()

```
virtual const char* IpxGenParam::Float::GetUnit (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the Unit.

## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the units</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

## Returns

Returns the measurement unit string

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

## 7.11 IpGui::IpGenParamTreeView Class Reference

[IpGenParamTreeView](#) class represents the GenICam parameters node tree panel.

```
#include <IpxCameraGuiApi.h>
```

## Public Member Functions

- virtual [~IpGenParamTreeView](#) ()  
*A destructor of the [IpGenParamTreeView](#) class.*
- virtual void [setParams](#) ([IpGenParam::Array](#) \*genParam)=0  
*Sets the [IpGenParam::Array](#) object to the node tree GUI.*
- virtual void [setParams](#) (`IPX_GENAPI_NS::INodeMap` \*nodemap)=0  
*Sets the [GenApi::INodeMap](#) object to the node tree GUI.*
- virtual void [clearParams](#) ()=0  
*Clears the parameters of the node tree GUI.*
- virtual [Visibility](#) [visibility](#) () const =0  
*This method returns the current visibility mode.*
- virtual void [setVisibility](#) ([Visibility](#) [visibility](#))=0  
*This method sets visibility mode.*
- virtual const char \* [saveState](#) () const =0  
*Saves the current state of the Tree View.*
- virtual void [loadState](#) (const char \*state)=0  
*Loads the state of the Tree View.*
- virtual void [setPollingTime](#) (`uint64_t` pollingTime)=0  
*Sets the polling time.*
- virtual `uint64_t` [getPollingTime](#) ()=0  
*Retrieves current polling time.*
- virtual void [enablePolling](#) (bool enable)=0  
*Enables the polling.*
- virtual bool [isPollingEnabled](#) ()=0  
*Retrieves current polling state.*

### 7.11.1 Detailed Description

[IpxGenParamTreeView](#) class represents the GenICam parameters node tree panel.

The [IpxGenParamTreeView](#) class is composed of functions to set and clear parameters of the GenICam parameters node tree of the camera. The node tree can be set with the current parameters stored in the [IpxGenParam::Array](#) and [GenApi::INodeMap](#) class.

For example, we can declare the instance of [IpxGui::IpxGenParamTreeView](#) class as `m_parameterView` as shown below:

```
IpxGui::IpxGenParamTreeView* m_ParameterView;
```


### 7.11.2 Constructor & Destructor Documentation

#### 7.11.2.1 ~IpxGenParamTreeView()

```
virtual IpxGui::IpxGenParamTreeView::~~IpxGenParamTreeView ( ) [inline], [virtual]
```

A destructor of the [IpxGenParamTreeView](#) class.

Destroys the [IpxGenParamTreeView](#) object and all its descendants. Here is the call graph for this function:



### 7.11.3 Member Function Documentation



## 7.11.3.1 setParams() [1/2]

```
virtual void IpxGui::IpxGenParamTreeView::setParams (
    IpxGenParam::Array * genParam ) [pure virtual]
```

Sets the [IpxGenParam::Array](#) object to the node tree GUI.

This method sets the parameters of the node tree by the information extracted from the [IpxGenParam::Array](#) class

## Parameters

in	<i>genParam</i>	The pointer to the <a href="#">IpxGenParam::Array</a> class.
----	-----------------	--

## Returns

void

For example, set the Camera Parameters to the corresponding fields of the TreeView as shown below:

```
// Establish camera device
m_camera = IpxCam_CreateDevice(m_devInfo);

// If the camera exist, set the camera parameter to the corresponding fields of the GUI TreeView
if(m_camera){
    m_ParameterView->setParams(m_camera->GetCameraParameters());
}
```

## 7.11.3.2 setParams() [2/2]

```
virtual void IpxGui::IpxGenParamTreeView::setParams (
    IPX_GENAPI_NS::INodeMap * nodemap ) [pure virtual]
```

Sets the GenApi::INodeMap object to the node tree GUI.

This method sets the parameters of the node tree with parameters retrieved from the GenApi::INodeMap class The INodeMap consists of a list of nodes representing the GenICam compliant camera high-level features.

## Parameters

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
----	----------------	--

## Returns

Void.

For example, setting the parameters of the node map.

```

// Instantiate the IpxGui::IIPxGenParamTreeView
IpxGui::IIPxGenParamTreeView* m_ParameterView;
...
auto params = GetCameraParameters(&retErr);
if(!params) {
    return retErr;
}
GenApi::INodeMap *nodemap = param->GetNodeMap(&retErr);
if(!nodemap){
    return retErr;
}
...
// Set the nodemap parameters of the GUI TreeView

m_ParameterView->setParams(nodemap);
...

```

### 7.11.3.3 clearParams()

```
virtual void IpxGui::IIPxGenParamTreeView::clearParams ( ) [pure virtual]
```

Clears the parameters of the node tree GUI.

This method clears the parameters of the node tree that have been set by the instance of the [IpxGui::IIPxGenParamTreeView](#) class

#### Returns

void.

For example, clear all the parameters after we disconnect the camera as shown below:

```

// Instantiate the IpxGui::IIPxGenParamTreeView
IpxGui::IIPxGenParamTreeView* m_ParameterView;

// Connect the camera
...
// Set some camera parameters
...
// Perform some actions
...
// Clear parameters during disconnecting process of camera
m_ParameterView->clearParam();

```

### 7.11.3.4 visibility()

```
virtual Visibility IpxGui::IIPxGenParamTreeView::visibility ( ) const [pure virtual]
```

This method returns the current visibility mode.

This method retrieves the current setting of the user visibility level for the feature

#### Returns

Visibility value

#### 7.11.3.5 setVisibility()

```
virtual void IpxGui::IIPxGenParamTreeView::setVisibility (
    Visibility visibility ) [pure virtual]
```

This method sets visibility mode.

It sets the current visibility level for the feature.

##### Parameters

in	<i>visibility</i>	The visibility mode value to set
----	-------------------	----------------------------------

##### Returns

Void.

#### 7.11.3.6 saveState()

```
virtual const char* IpxGui::IIPxGenParamTreeView::saveState ( ) const [pure virtual]
```

Saves the current state of the Tree View.

This method creates the string, representing the current state of the Tree View, and returns the pointer to this string.

##### Returns

If succeeds, the method returns pointer to the state string. Otherwise, the return value is nullptr. The string consists of sub-string values separated by the token. Just save this data somewhere if you want to restore the state later.

#### 7.11.3.7 loadState()

```
virtual void IpxGui::IIPxGenParamTreeView::loadState (
    const char * state ) [pure virtual]
```

Loads the state of the Tree View.

This method loads the state of the Tree View using the string, created by [saveState\(\)](#) method. The individual node can be in expanded or collapse state.

**Parameters**

in	<i>state</i>	State string to be loaded. The string consists of sub-string values separated by the token.
----	--------------	---

**7.11.3.8 setPollingTime()**

```
virtual void IpxGui::IIPxGenParamTreeView::setPollingTime (
    uint64_t pollingTime ) [pure virtual]
```

Sets the polling time.

This method sets the value of the parameters pooling time. Polling should be enabled by [enablePolling\(\)](#) function

**Parameters**

in	<i>pollingTime</i>	time in msec to be set
----	--------------------	------------------------

**7.11.3.9 getPollingTime()**

```
virtual uint64_t IpxGui::IIPxGenParamTreeView::getPollingTime ( ) [pure virtual]
```

Retrieves current polling time.

This method retrieves the value of the parameters polling time. Polling should be enabled by [enablePolling\(\)](#) function

**Returns**

current polling time in msec

The documentation for this class was generated from the following file:


- IpxCameraGuiApi.h

## 7.12 IpxGenParam::Int Class Reference

A class containing methods for Integer GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Int:



### Public Member Functions

- virtual [ParamType GetType](#) ()  
*This method returns the node object [Int](#) type.*
- virtual IpxCamErr [SetValue](#) (int64\_t val)=0  
*This method sets the [Int](#) node value.*
- virtual int64\_t [GetValue](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the [Int](#) node value.*
- virtual int64\_t [GetMin](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the minimum value.*
- virtual int64\_t [GetMax](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the maximum value.*
- virtual int64\_t [GetIncrement](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the Increment value.*

### 7.12.1 Detailed Description

A class containing methods for Integer GenICam camera parameter.

A class containing methods to access the Integer GenICam camera parameter as integer value.

For example, the mapping below illustrates "Width" Integer parameter.

## 7.12.2 Member Function Documentation

### 7.12.2.1 GetType()

```
virtual ParamType IpxGenParam::Int::GetType ( ) [inline], [virtual]
```

This method returns the node object [Int](#) type.

#### Returns

Returns the parameter type

Implements [IpxGenParam::Param](#).

### 7.12.2.2 SetValue()

```
virtual IpxCamErr IpxGenParam::Int::SetValue (
    int64_t val ) [pure virtual]
```

This method sets the [Int](#) node value.

#### Parameters

in	val	<a href="#">Int</a> node value
----	-----	--------------------------------

#### Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Int](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

### 7.12.2.3 GetValue()

```
virtual int64_t IpxGenParam::Int::GetValue (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the [Int](#) node value.

## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the <a href="#">Int</a> value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

## Returns

Returns the [Int](#) node value

## 7.12.2.4 GetMin()

```
virtual int64_t IpxGenParam::Int::GetMin (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the minimum value.

## Parameters

out	err	returns error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Minimum int value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>
-----	-----	---

## Returns

Returns the minimum

## 7.12.2.5 GetMax()

```
virtual int64_t IpxGenParam::Int::GetMax (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the maximum value.

**Parameters**

out	err	returns error code:
		<ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Maximum int value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

**Returns**

Returns the maximum

**7.12.2.6 GetIncrement()**

```
virtual int64_t IpxGenParam::Int::GetIncrement (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the Increment value.

**Parameters**

out	err	returns error code :
		<ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the increment value</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

**Returns**

Returns the increment

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

**7.13 IpxCam::Interface Class Reference**

The [Interface](#) class represents a interface module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```



## Public Member Functions

- virtual [~Interface](#) ()  
*Interface class destructor.*
- virtual [DeviceInfoList](#) \* [GetDeviceInfoList](#) ()=0  
*This method retrieves the list of [DeviceInfo](#) objects for the camera devices, available on this [Interface](#).*
- virtual [DeviceInfo](#) \* [GetFirstDeviceInfo](#) ()=0  
*This method retrieves the [DeviceInfo](#) object for the first device available on this [Interface](#).*
- virtual [DeviceInfo](#) \* [GetDeviceInfoById](#) (const char \*deviceId)=0  
*This method retrieves the [DeviceInfo](#) object pointer for the specified device identifier.*
- virtual [lpxCamErr](#) [ReEnumerateDevices](#) (bool \*pChanged, uint64\_t iTimeout)=0  
*This method re-enumerates the devices.*
- virtual const char \* [GetDescription](#) ()=0  
*This method returns the description of the interface.*
- virtual [InterfaceType](#) [GetType](#) ()=0  
*This method gets the type of interface.*
- virtual const char \* [GetId](#) ()=0  
*This method gets the identifier of the interface .*
- virtual const char \* [GetVersion](#) ()=0  
*This method gets the version of [Interface](#) driver.*
- virtual [lpxCamErr](#) [RegisterEvent2](#) (uint32\_t eventType, [lpxCam::EventCallback2](#) \*eventCallback, void \*p↔Private)=0  
*This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.*
- virtual [lpxCamErr](#) [RegisterEvent](#) (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0  
*This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.*
- virtual [lpxCamErr](#) [UnRegisterEvent2](#) (uint32\_t eventType, [lpxCam::EventCallback2](#) \*eventCallback, void \*p↔Private)=0  
*This method unregisters the [Interface](#) class callback method for the eventType.*
- virtual [lpxCamErr](#) [UnRegisterEvent](#) (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*p↔Private)=0  
*This method unregisters the [Interface](#) class callback method for the eventType.*
- virtual [lpxGenParam::Array](#) \* [GetParameters](#) ([lpxCamErr](#) \*err=nullptr)=0  
*This method returns the parameter array used to control the Imperx Camera device.*
- virtual [Device](#) \* [CreateDeviceFromConfig](#) (const char \*fileName, [lpxCamErr](#) \*err=nullptr)=0  
*Creates the [Device](#) object from configuration file.*

### 7.13.1 Detailed Description

The [Interface](#) class represents a interface module in the GenTL module hierarchy.

This class represents an individual physical interface in the [System](#). For example, a network interface card (NIC) for GigE Vision connection, CXP or Camera Link frame grabber board, or USB3 Vision driver in the GenTL system. The [Interface](#) class includes methods to enumerate the available devices on the physical interface in the system.

### 7.13.2 Constructor & Destructor Documentation

### 7.13.2.1 ~Interface()

```
virtual IpxCam::Interface::~~Interface ( ) [inline], [virtual]
```

[Interface](#) class destructor.

Destroys the [Interface](#) object and all its descendants.

## 7.13.3 Member Function Documentation

### 7.13.3.1 GetDeviceInfoList()

```
virtual DeviceInfoList* IpxCam::Interface::GetDeviceInfoList ( ) [pure virtual]
```

This method retrieves the list of [DeviceInfo](#) objects for the camera devices, available on this [Interface](#).

#### Returns

Returns the pointer to DeviceInfoList object

For example,

```
// Get the Device Info List for the Interface
// List has to be released, let us use unique pointer
auto del = [](IpxCam::DeviceInfoList *l) { l->Release(); };
std::unique_ptr<IpxCam::DeviceInfoList, decltype(del)> list(iface->GetDeviceInfoList(), del);

if (list->GetCount() == 0)
{
    std::cout << "No Interface Available. " << endl;
    exit(1);
}

IpxCam::Device *device = nullptr;
for (auto devInfo = list->GetFirst(); devInfo; devInfo = list->GetNext())
{
    if (std::string("Test camera") == devInfo->GetModel())
    {
        device = IpxCam::IpxCam_CreateDevice(devInfo);
        break;
    }
}
```

## 7.13.3.2 GetFirstDeviceInfo()

```
virtual DeviceInfo* IpxCam::Interface::GetFirstDeviceInfo ( ) [pure virtual]
```

This method retrieves the [DeviceInfo](#) object for the first device available on this [Interface](#).

## Returns

Returns the pointer to [DeviceInfo](#) object or nullptr if no device found

For example,

```
//Retrieve the first device available for the specified interface.
lDeviceInfo = iface->GetFirstDeviceInfo();

std::cout << "First Device Info ModelName" << lDeviceInfo->GetModel() << endl;
```

## 7.13.3.3 GetDeviceInfoById()

```
virtual DeviceInfo* IpxCam::Interface::GetDeviceInfoById (
    const char * deviceId ) [pure virtual]
```

This method retrieves the [DeviceInfo](#) object pointer for the specified device identifier.

## Parameters

in	<i>deviceId</i>	<a href="#">Device</a> identifier
----	-----------------	-----------------------------------

## Returns

Returns the pointer to [DeviceInfo](#) object or nullptr if no such device found

## 7.13.3.4 ReEnumerateDevices()

```
virtual IpxCamErr IpxCam::Interface::ReEnumerateDevices (
    bool * pChanged,
    uint64_t iTimeout ) [pure virtual]
```

This method re-enumerates the devices.

The ReEnumerateDevices method allows the user to re-enumerate the devices connected to the [Interface](#) and update the DeviceInfoList object returned by subsequent [GetDeviceInfoList\(\)](#) method calls.

**Parameters**

in	<i>pChanged</i>	Change in <a href="#">Device</a>
in	<i>iTimeout</i>	Timeout allowed to search for available camera devices

**Returns**

Returns error code

**7.13.3.5 GetDescription()**

```
virtual const char* IpxCam::Interface::GetDescription ( ) [pure virtual]
```

This method returns the description of the interface.

The GetDescription method gets the user readable string description of the interface.

**Returns**

Returns the Description of the interface

**7.13.3.6 GetType()**

```
virtual InterfaceType IpxCam::Interface::GetType ( ) [pure virtual]
```

This method gets the type of interface.

The GetType method returns the [Interface](#) Type (Transport Layer Technology) of this interface object

**Returns**

Returns [Interface](#) Type

The interface type return can be the following:

```
enum InterfaceType
{
    USB3Vision    = 1,
    GigEVision    = 2,
    CameraLink    = 3,
    CoaxPress     = 4,
    HdSdi         = 5,
    AllInterfaces = 0xff,
};
```

#### 7.13.3.7 GetId()

```
virtual const char* IpxCam::Interface::GetId ( ) [pure virtual]
```

This method gets the identifier of the interface .

The GetId method returns the interface identifier that could be used to instantiate the interface object

##### Returns

Returns interface identifier

#### 7.13.3.8 GetVersion()

```
virtual const char* IpxCam::Interface::GetVersion ( ) [pure virtual]
```

This method gets the version of [Interface](#) driver.

Returns the pointer to the string with the version of the interface driver

##### Returns

Returns the version of the interface driver

#### 7.13.3.9 RegisterEvent2()

```
virtual IpxCamErr IpxCam::Interface::RegisterEvent2 (
    uint32_t eventType,
    IpxCam::EventCallback2 * eventCallback,
    void * pPrivate ) [pure virtual]
```

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

##### Parameters

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	pointer to event CallBack method
in	<i>pPrivate</i>	pointer to user's data

**Returns**

Returns Error code

**7.13.3.10 RegisterEvent()**

```
virtual IpxCamErr IpxCam::Interface::RegisterEvent (
    uint32_t eventType,
    IpxCam::EventCallback * eventCallback,
    void * pPrivate ) [pure virtual]
```

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

**Deprecated** Use RegisterEvent2 instead

**7.13.3.11 UnRegisterEvent2()**

```
virtual IpxCamErr IpxCam::Interface::UnRegisterEvent2 (
    uint32_t eventType,
    IpxCam::EventCallback2 * eventCallback,
    void * pPrivate ) [pure virtual]
```

This method unregisters the [Interface](#) class callback method for the eventType.

**Parameters**

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	pointer to event CallBack method
in	<i>pPrivate</i>	pointer to user's data

**Returns**

Returns Error code

**7.13.3.12 UnRegisterEvent()**

```
virtual IpxCamErr IpxCam::Interface::UnRegisterEvent (
    uint32_t eventType,
```

```
IpxCam::EventCallback * eventCallback,  
void * pPrivate ) [pure virtual]
```

This method unregisters the [Interface](#) class callback method for the eventType.

**Deprecated** Use UnRegisterEvent2 instead

#### 7.13.3.13 GetParameters()

```
virtual IpxGenParam::Array* IpxCam::Interface::GetParameters (  
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method returns the parameter array used to control the Imperx Camera device.

##### Parameters

out	<i>err</i>	returns error code
-----	------------	--------------------

##### Returns

Returns the pointer to [IpxGenParam::Array](#) object, used to control the Imperx Camera device

#### 7.13.3.14 CreateDeviceFromConfig()

```
virtual Device* IpxCam::Interface::CreateDeviceFromConfig (  
    const char * fileName,  
    IpxCamErr * err = nullptr ) [pure virtual]
```

Creates the [Device](#) object from configuration file.

This method creates, configures and sets up the device using the information retrieved from the specified configuration file

##### Parameters

in	<i>fileName</i>	Configuration file to open
out	<i>err</i>	returns error code

##### Returns

Returns [Device](#) or nullptr if device cannot be instantiated

The documentation for this class was generated from the following file:

- IpxCameraApi.h

## 7.14 IpxCam::List<\_T> Class Template Reference

The [List](#) class is used as list-like container for the specified template type objects.

```
#include <IpxCameraApi.h>
```

### Public Types

- typedef [\\_T](#) [elem\\_type](#)

### Public Member Functions

- virtual [~List](#) ()  
*A destructor of the [List](#) class.*
- virtual void [Release](#) ()=0  
*This method releases the instance of the list of the specified object.*
- virtual size\_t [GetCount](#) ()=0  
*This functions gets the number of items in the specified list object.*
- virtual [elem\\_type](#) \* [GetFirst](#) ()=0  
*This method retrieves the first element in the specified list object.*
- virtual [elem\\_type](#) \* [GetNext](#) ()=0  
*This method retrieves the next element in the specified list object.*

#### 7.14.1 Detailed Description

```
template<class _T>
class IpxCam::List<_T>
```

The [List](#) class is used as list-like container for the specified template type objects.

The supported template type objects are [Interface](#), [Device](#), [DeviceInfo](#), [Stream](#), and [Buffer](#).

They can be declared as follows:

<b>IpxCam::List&lt;Interface&gt; *interfaceList</b>	<b>This class represents the list of <a href="#">Interface</a> objects.</b>
<b>IpxCam::List&lt;Device&gt; *deviceList</b>	<b>This class represents the list of <a href="#">Device</a> objects.</b>
<b>IpxCam::List&lt;DeviceInfo&gt; *deviceInfoList</b>	<b>This class represents the list of <a href="#">DeviceInfo</a> objects.</b>
<b>IpxCam::List&lt;Stream&gt; *streamList</b>	<b>This class represents the list of Data <a href="#">Stream</a> objects</b>
<b>IpxCam::List&lt;Buffer&gt; *bufferList</b>	<b>This class represents the list of <a href="#">Buffer</a> objects</b>



Alternatively, you can also use the declared typedef (aliases for specific objects) provided in the `IpxCam` namespace as shown below:

```
typedef List<Interface>      InterfaceList;
typedef List<DeviceInfo>    DeviceInfoList;
typedef List<Device>        DeviceList;
```

They can be declared as follows:

<b>InterfaceList *interfaceList</b>	This class represents the list of <b>Interface</b> objects.
<b>DeviceInfoList *deviceInfoList</b>	This class represents the list of <b>DeviceInfo</b> objects.

This class can be used to search through the list of objects discovered.

### Example using DeviceInfoList

In this example, you will see how to use the DeviceInfoList. An example is shown below that demonstrates on how to use the list class methods. The `deviceInfoList->GetCount()` method is used retrieve the number of devices connected. We confirm that at least one device is available. Next, the for loop will loop from the first device information listed using the `deviceInfoList->GetFirst()` function to the end of the list. During each iteration the `deviceInfoList->GetNext()` will increment to the next deviceInfo available. In the example, you will notice that we search for a specified device model name. Once, the specified device is found, we will release the `deviceInfoList->Release()` and the create the specified device using the `IpxCam::IpxCam_CreateDevice()` method.

```
// Get the Device Info List for the Interface
// List has to be released, let us use unique pointer
auto del = [] (IpxCam::DeviceInfoList *l) { l->Release(); };
std::unique_ptr<IpxCam::DeviceInfoList, decltype(del)> list(iface->GetDeviceInfoList(), del);

if (list->GetCount() == 0)
{
    std::cout << "No Interface Available. " << endl;
    exit(1);
}

IpxCam::Device *device = nullptr;
for (auto devInfo = list->GetFirst(); devInfo; devInfo = list->GetNext())
{
    if (std::string("Test camera") == devInfo->GetModel())
    {
        device = IpxCam::IpxCam_CreateDevice(devInfo);
        break;
    }
}
```

### Example using InterfaceList

In this example, you will see how to use the InterfaceList. You will retrieve the interfaces available for this system. Next, the for loop will loop from the first interface available using the `list->GetFirst()` method to the end of the list. During each iteration the `list->GetNext()` will increment to the next interface available.

```
// Used later to get chosen interface
std::vector<IpxCam::Interface*> ifaceVector;

// Get the Interface List for the System
auto list = system->GetInterfaceList();
```

```
// Get the individual Interface elements
for (auto iface = list->GetFirst(); iface; iface = list->GetNext())
{
    ifaceVector.push_back(iface);

    // Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->GetDescription() << "Id " << iface
        ->GetId() << endl;
}

// List has to be released
list->Release();
```

## 7.14.2 Member Typedef Documentation

### 7.14.2.1 elem\_type

```
template<class _T >
typedef _T IpxCam::List< _T >::elem_type
```

Element Type

## 7.14.3 Constructor & Destructor Documentation

### 7.14.3.1 ~List()

```
template<class _T >
virtual IpxCam::List< _T >::~~List ( ) [inline], [virtual]
```

A destructor of the [List](#) class.

Destructor. Destroys the [List](#) object and all its descendants.

## 7.14.4 Member Function Documentation

#### 7.14.4.1 Release()

```
template<class _T >
virtual void IpxCam::List<_T>::Release ( ) [pure virtual]
```

This method releases the instance of the list of the specified object.

##### Returns

Void.

#### 7.14.4.2 GetCount()

```
template<class _T >
virtual size_t IpxCam::List<_T>::GetCount ( ) [pure virtual]
```

This functions gets the number of items in the specified list object.

##### Returns

Returns the number of items in the specified list object.

#### 7.14.4.3 GetFirst()

```
template<class _T >
virtual elem_type* IpxCam::List<_T>::GetFirst ( ) [pure virtual]
```

This method retrieves the first element in the specified list object.

##### Returns

Returns the first element in the specified list object.

#### 7.14.4.4 GetNext()

```
template<class _T >
virtual elem_type* IpxCam::List<_T>::GetNext ( ) [pure virtual]
```

This method retrieves the next element in the specified list object.

##### Returns

Returns the next element in the specified list object.

The documentation for this class was generated from the following file:


- IpxCameraApi.h

## 7.15 IpxGenParam::Param Class Reference

General class for GenICam parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Param:



### Public Member Functions

- virtual `~Param()`  
*Param* class destructor. Destroys the *Param* and all its descendants.
- virtual `ParamType GetType()`=0  
*This method returns the Parameter Node Type.*
- virtual const char \* `GetName()`=0  
*This method returns the parameter node name.*
- virtual const char \* `GetToolTip()`=0  
*This method returns a short description of the parameter node.*
- virtual const char \* `GetDescription()`=0

- This method returns a long description of the parameter node.*

  - virtual const char \* [GetDisplayName](#) ()=0

*This method returns the string to be used for the parameter displaying.*
- virtual [Visibility](#) [GetVisibility](#) ()=0

*This method returns the visibility of the node.*
- virtual bool [IsValueCached](#) ()=0

*This method checks if the parameter node is cached.*
- virtual bool [IsAvailable](#) ()=0

*This method checks if parameter node is available.*
- virtual bool [IsWritable](#) ()=0

*This method checks if parameter node is writable.*
- virtual bool [IsReadable](#) ()=0

*This method checks if the parameter node is readable.*
- virtual bool [IsStreamable](#) ()=0

*This method checks if the parameter node is streamable.*
- virtual bool [IsVisible](#) ([Visibility](#) vis)=0

*This method checks if the node is visible.*
- virtual lpxCamErr [RegisterEventSink](#) ([ParamEventSink](#) \*aEventSink)=0

*This method registers the event.*
- virtual lpxCamErr [UnregisterEventSink](#) ([ParamEventSink](#) \*aEventSink)=0

*This method unregisters the event.*
- virtual IPX\_GENAPI\_NS::INode \* [GetNode](#) ()=0

*This method returns the callback of the node registered.*
- virtual [Category](#) \* [ToCategory](#) ()=0

*This method returns typed representation of param.*
- virtual [Boolean](#) \* [ToBoolean](#) ()=0

*This method returns typed representation of param.*
- virtual [Command](#) \* [ToCommand](#) ()=0

*This method returns typed representation of param.*
- virtual [EnumEntry](#) \* [ToEnumEntry](#) ()=0

*This method returns typed representation of param.*
- virtual [Enum](#) \* [ToEnum](#) ()=0

*This method returns typed representation of param.*
- virtual [Float](#) \* [ToFloat](#) ()=0

*This method returns typed representation of param.*
- virtual [Int](#) \* [ToInt](#) ()=0

*This method returns typed representation of param.*
- virtual [String](#) \* [ToString](#) ()=0

*This method returns typed representation of param.*

### 7.15.1 Detailed Description

General class for GenICam parameter.

Class for accessing the GenICam feature node of the Camera parameters

## 7.15.2 Constructor & Destructor Documentation

### 7.15.2.1 ~Param()

```
virtual IpxGenParam::Param::~~Param ( ) [inline], [virtual]
```

[Param](#) class destructor. Destroys the [Param](#) and all its descendants.

[Param](#) class destructor.

## 7.15.3 Member Function Documentation

### 7.15.3.1 GetType()

```
virtual ParamType IpxGenParam::Param::GetType ( ) [pure virtual]
```

This method returns the Parameter Node Type.

#### Returns

return the parameter type.

Implemented in [IpxGenParam::String](#), [IpxGenParam::Int](#), [IpxGenParam::Float](#), [IpxGenParam::Enum](#), [IpxGenParam::EnumEntry](#), [IpxGenParam::Command](#), [IpxGenParam::Boolean](#), and [IpxGenParam::Category](#).

### 7.15.3.2 GetName()

```
virtual const char* IpxGenParam::Param::GetName ( ) [pure virtual]
```

This method returns the parameter node name.

#### Returns

If the method succeeds, it will return the parameter node name. Otherwise, it will return a nullptr.

#### 7.15.3.3 GetToolTip()

```
virtual const char* IpxGenParam::Param::GetToolTip ( ) [pure virtual]
```

This method returns a short description of the parameter node.

##### Returns

If the method succeeds, it will return a short description of the parameter node. Otherwise, it will return a nullptr.

#### 7.15.3.4 GetDescription()

```
virtual const char* IpxGenParam::Param::GetDescription ( ) [pure virtual]
```

This method returns a long description of the parameter node.

##### Returns

If the method succeeds, it will return a long description of the parameter node. Otherwise, it will return a nullptr.

#### 7.15.3.5 GetDisplayName()

```
virtual const char* IpxGenParam::Param::GetDisplayName ( ) [pure virtual]
```

This method returns the string to be used for the parameter displaying.

##### Returns

If the method succeeds, it will return the parameter display name. Otherwise, it will return a nullptr.

#### 7.15.3.6 GetVisibility()

```
virtual Visibility IpxGenParam::Param::GetVisibility ( ) [pure virtual]
```

This method returns the visibility of the node.

##### Returns

It will return the visibility setting of the parameter node. It will be either Basic, Expert, or Guru.

#### 7.15.3.7 IsValueCached()

```
virtual bool IpxGenParam::Param::IsValueCached ( ) [pure virtual]
```

This method checks if the parameter node is cached.

##### Returns

True if the value is cached. False if the value is not cached.

#### 7.15.3.8 IsAvailable()

```
virtual bool IpxGenParam::Param::IsAvailable ( ) [pure virtual]
```

This method checks if parameter node is available.

##### Returns

True if the parameter node is available. False if it is not available.

#### 7.15.3.9 IsWritable()

```
virtual bool IpxGenParam::Param::IsWritable ( ) [pure virtual]
```

This method checks if parameter node is writable.

##### Returns

True if the parameter node is writable. False if it is not writable.

#### 7.15.3.10 IsReadable()

```
virtual bool IpxGenParam::Param::IsReadable ( ) [pure virtual]
```

This method checks if the parameter node is readable.

##### Returns

True if the parameter node is readable. False if it is not readable.



#### 7.15.3.11 IsStreamable()

```
virtual bool IpxGenParam::Param::IsStreamable ( ) [pure virtual]
```

This method checks if the parameter node is streamable.

##### Returns

True if the parameter node is streamable. False if it is not streamable.

#### 7.15.3.12 IsVisible()

```
virtual bool IpxGenParam::Param::IsVisible (
    Visibility vis ) [pure virtual]
```

This method checks if the node is visible.

##### Parameters

in	vis	Visibility of the parameter node
----	-----	----------------------------------

##### Returns

True if the parameter node is visible. False if it is not visible.

#### 7.15.3.13 RegisterEventSink()

```
virtual IpxCamErr IpxGenParam::Param::RegisterEventSink (
    ParamEventSink * aEventSink ) [pure virtual]
```

This method registers the event.

##### Parameters

in	aEventSink	pointer to Parameter Event Sink
----	------------	---------------------------------

##### Returns

Returns the Error code:

- IpxCamErr::IPX\_CAM\_ERR\_OK - Successfully registers event sink

#### 7.15.3.14 UnregisterEventSink()

```
virtual IpxCamErr IpxGenParam::Param::UnregisterEventSink (
    ParamEventSink * aEventSink ) [pure virtual]
```

This method unregisters the event.

##### Parameters

in	<i>aEventSink</i>	pointer to Parameter Event Sink
----	-------------------	---------------------------------

##### Returns

Returns the Error code:

- IpxCamErr::IPX\_CAM\_ERR\_OK - Successfully unregisters event sink

#### 7.15.3.15 GetNode()

```
virtual IPX_GENAPI_NS::INode* IpxGenParam::Param::GetNode ( ) [pure virtual]
```

This method returns the callback of the node registered.

##### Returns

If the method succeeds, it will return the pointer to the node of the callback that is registered. Otherwise, it will return a value of nullptr.

#### 7.15.3.16 ToCategory()

```
virtual Category* IpxGenParam::Param::ToCategory ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.17 ToBoolean()

```
virtual Boolean* IpxGenParam::Param::ToBoolean ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.18 ToCommand()

```
virtual Command* IpxGenParam::Param::ToCommand ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.19 ToEnumEntry()

```
virtual EnumEntry* IpxGenParam::Param::ToEnumEntry ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.20 ToEnum()

```
virtual Enum* IpxGenParam::Param::ToEnum ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.21 ToFloat()

```
virtual Float* IpxGenParam::Param::ToFloat ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.22 ToInt()

```
virtual Int* IpxGenParam::Param::ToInt ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

#### 7.15.3.23 ToString()

```
virtual String* IpxGenParam::Param::ToString ( ) [pure virtual]
```

This method returns typed representation of param.

##### Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

The documentation for this class was generated from the following file:

- IpxCameraApi.h

## 7.16 IpxGenParam::ParamEventSink Class Reference

A Class for [ParamEventSink](#) notifications handling.

```
#include <IpxCameraApi.h>
```

## Public Member Functions

- virtual [~ParamEventSink](#) ()  
*[ParamEventSink](#) class destructor. Destroys the [ParamEventSink](#) object and all its descendants.*
- virtual void [OnParameterUpdate](#) ([Param](#) \*param)=0  
*Update Parameter Node.*

### 7.16.1 Detailed Description

A Class for [ParamEventSink](#) notifications handling.

An Event Sink class designed to receive the notifications from the GenICam parameter Node Updates

### 7.16.2 Member Function Documentation

#### 7.16.2.1 OnParameterUpdate()

```
virtual void IpxGenParam::ParamEventSink::OnParameterUpdate (
    Param * param ) [pure virtual]
```

Update Parameter Node.

#### Parameters

in	<i>param</i>	The pointer to the <a href="#">Param</a> class node
----	--------------	---

#### Returns

Void.

The documentation for this class was generated from the following file:

- IpxCameraApi.h

## 7.17 IpxCam::Stream Class Reference

The [Stream](#) class represents the data stream module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

## Public Member Functions

- virtual [~Stream](#) ()  
*A destructor of the [Stream](#) class.*
- virtual void [Release](#) ()=0  
*This method releases the instance of the stream object.*
- virtual [lpxCam::Buffer](#) \* [CreateBuffer](#) (size\_t iSize, void \*pPrivate, lpxCamErr \*err)=0  
*Creates the buffer in the data stream object.*
- virtual [lpxCam::Buffer](#) \* [SetBuffer](#) (void \*pBuffer, size\_t iSize, void \*pPrivate, lpxCamErr \*err)=0  
*Sets memory buffer to create the [Buffer](#) object.*
- virtual lpxCamErr [RevokeBuffer](#) ([lpxCam::Buffer](#) \*buff)=0  
*Revokes any announced buffer.*
- virtual lpxCamErr [QueueBuffer](#) ([lpxCam::Buffer](#) \*buff)=0  
*This method queues specified buffers.*
- virtual [lpxCam::Buffer](#) \* [GetBuffer](#) (uint64\_t iTimeout, lpxCamErr \*err=nullptr)=0  
*This method retrieves the buffer object.*
- virtual lpxCamErr [CancelBuffer](#) ()=0  
*Terminates the waiting operation on a previously queued [Buffer](#).*
- virtual lpxCamErr [FlushBuffers](#) ([FlushOperation](#) operation)=0  
*This method flushes the buffers of the data stream object.*
- virtual lpxCamErr [StartAcquisition](#) (uint64\_t iNumFramesToAcquire=UINT64\_MAX, uint32\_t flags=0)=0  
*Starts the Acquisition Engine.*
- virtual lpxCamErr [StopAcquisition](#) (uint32\_t flags=0)=0  
*Stops the stream's acquisition engine.*
- virtual lpxCamErr [AllocBufferQueue](#) (void \*pPrivate, size\_t iNum)=0  
*Allocates the [Buffer](#) Queue.*
- virtual lpxCamErr [ReleaseBufferQueue](#) ()=0  
*Releases the [Buffer](#) Queue.*
- virtual size\_t [GetBufferQueueSize](#) ()=0  
*Retrieves the [Buffer](#) Queue size.*
- virtual lpxCamErr [RegisterEvent](#) (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0  
*Registers the EventCallback.*
- virtual lpxCamErr [UnRegisterEvent](#) (uint32\_t eventType, [lpxCam::EventCallback](#) \*eventCallback, void \*pPrivate)=0  
*Unregisters the EventCallback.*
- virtual [lpxGenParam::Array](#) \* [GetParameters](#) (lpxCamErr \*err=nullptr)=0  
*Returns the GenICam parameters array.*
- virtual uint64\_t [GetNumDelivered](#) ()=0  
*Returns the number of the delivered buffers.*
- virtual uint64\_t [GetNumUnderrun](#) ()=0  
*Returns the number under-run frames.*
- virtual size\_t [GetNumAnnounced](#) ()=0  
*Returns the number of announced buffers.*
- virtual size\_t [GetNumQueued](#) ()=0  
*Returns the number of queued buffers.*
- virtual size\_t [GetNumAwaitDelivery](#) ()=0  
*Returns the number of buffers awaiting delivery.*

- virtual size\_t [GetBufferSize](#) ()=0  
*Returns the buffer size.*
- virtual bool [IsGrabbing](#) ()=0  
*This method returns a flag indicating if the data stream is grabbing or not.*
- virtual size\_t [GetMinNumBuffers](#) ()=0  
*Returns the minimum number of buffers to be announced.*
- virtual size\_t [GetBufferAlignment](#) ()=0  
*Returns the buffer alignment size.*

### 7.17.1 Detailed Description

The [Stream](#) class represents the data stream module in the GenTL module hierarchy.

This data stream class provides buffer methods. This data stream class purpose is to access the buffer data acquirement from the Acquisition engine.

### 7.17.2 Constructor & Destructor Documentation

#### 7.17.2.1 ~Stream()

```
virtual IpxCam::Stream::~Stream ( ) [inline], [virtual]
```

A destructor of the [Stream](#) class.

Destroys the [Stream](#) object and all its descendants.

### 7.17.3 Member Function Documentation

#### 7.17.3.1 Release()

```
virtual void IpxCam::Stream::Release ( ) [pure virtual]
```

This method releases the instance of the stream object.

**Returns**

void

#### 7.17.3.2 CreateBuffer()

```
virtual IpxCam::Buffer* IpxCam::Stream::CreateBuffer (
    size_t iSize,
    void * pPrivate,
    IpxCamErr * err ) [pure virtual]
```

Creates the buffer in the data stream object.

This method allocates the memory for a buffer and announces this buffer to the data stream

**Parameters**

in	<i>iSize</i>	Size of the buffer
in	<i>pPrivate</i>	pointer to private data (user's data) which will be passed to the GenTL Consumer
out	<i>err</i>	returns Error code

**Returns**

Returns [Buffer](#) object pointer of the announced buffer

**7.17.3.3 SetBuffer()**

```
virtual IpxCam::Buffer\* IpxCam::Stream::SetBuffer (
    void * pBuffer,
    size_t iSize,
    void * pPrivate,
    IpxCamErr * err ) [pure virtual]
```

Sets memory buffer to create the [Buffer](#) object.

This method is used to set the user-allocated memory buffer to create the [Buffer](#) object and announce it to the data stream.

**Parameters**

in	<i>pBuffer</i>	buffer
in	<i>iSize</i>	size of <a href="#">Buffer</a>
in	<i>pPrivate</i>	pointer to user's data
out	<i>err</i>	returns Error code

**Returns**

returns [Buffer](#) object pointer

**7.17.3.4 RevokeBuffer()**

```
virtual IpxCamErr IpxCam::Stream::RevokeBuffer (
    IpxCam::Buffer * buff ) [pure virtual]
```

Revokes any announced buffer.

This method removes the specified announced [Buffer](#) from the acquisition engine's queue



**Parameters**

in	<i>buff</i>	Buffer object pointer
----	-------------	-----------------------

**Returns**

Returns Error code

**7.17.3.5 QueueBuffer()**

```
virtual IpxCamErr IpxCam::Stream::QueueBuffer (  
    IpxCam::Buffer * buff ) [pure virtual]
```

This method queues specified buffers.

During the acquisition, this method is used to return the specified buffer to the acquisition engine's queue

**Parameters**

in	<i>buff</i>	Buffer object pointer
----	-------------	-----------------------

**Returns**

Returns Error code

**7.17.3.6 GetBuffer()**

```
virtual IpxCam::Buffer* IpxCam::Stream::GetBuffer (  
    uint64_t iTimeout,  
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method retrieves the buffer object.

Retrieves the next acquired buffer entry from the acquisition engine's queue and returns the acquired Buffer object

**Parameters**

in	<i>iTimeout</i>	timeout in ms
in	<i>err</i>	error code

**Returns**

Returns the pointer to the acquired [Buffer](#) object

**7.17.3.7 CancelBuffer()**

```
virtual IpxCamErr IpxCam::Stream::CancelBuffer ( ) [pure virtual]
```

Terminates the waiting operation on a previously queued [Buffer](#).

This method cancels the waiting operation on a previously queued [Buffer](#) in the acquisition engine's queue

**Returns**

Returns Error code

**7.17.3.8 FlushBuffers()**

```
virtual IpxCamErr IpxCam::Stream::FlushBuffers (
    FlushOperation operation ) [pure virtual]
```

This method flushes the buffers of the data stream object.

Performs the specified Flush Operation on the acquisition engine's queue. Operations type is defined in FlushOperations enum.

**Parameters**

in	<i>operation</i>	FlushOperation
----	------------------	----------------

**Returns**

Returns Error code

**7.17.3.9 StartAcquisition()**

```
virtual IpxCamErr IpxCam::Stream::StartAcquisition (
    uint64_t iNumFramesToAcquire = UINT64_MAX,
    uint32_t flags = 0 ) [pure virtual]
```

Starts the Acquisition Engine.

This method starts the acquisition engine of the stream to acquire the image data frames to the queued buffers

**Parameters**

in	<i>iNumFramesToAcquire</i>	number of Frames to Acquire. Set UINT64_MAX for the infinite acquisition
in	<i>flags</i>	flags. Set to 0 by default

**Returns**

Returns Error code

**7.17.3.10 StopAcquisition()**

```
virtual IpxCamErr IpxCam::Stream::StopAcquisition (  
    uint32_t flags = 0 ) [pure virtual]
```

Stops the stream's acquisition engine.

This method stops the acquisition engine of the stream and terminates the image data frames acquisition

**Parameters**

in	<i>flags</i>	flags: <ul style="list-style-type: none"><li>• ACQ_STOP_FLAGS_DEFAULT=0, Stop the acquisition engine when the currently running tasks like filling a buffer are completed (default behavior).</li><li>• ACQ_STOP_FLAGS_KILL=1, Stop the acquisition engine immediately and leave buffers currently being filled in the Input <a href="#">Buffer</a> Pool.</li></ul>
----	--------------	---

**Returns**

Returns Error code

**7.17.3.11 AllocBufferQueue()**

```
virtual IpxCamErr IpxCam::Stream::AllocBufferQueue (  
    void * pPrivate,  
    size_t iNum ) [pure virtual]
```

Allocates the [Buffer](#) Queue.

This method allocates the buffers in the queue of the acquisition engine of the data stream object.

**Parameters**

in	<i>pPrivate</i>	pointer to user's data
in	<i>iNum</i>	number of the buffers to allocate

**Returns**

Returns Error code

**7.17.3.12 ReleaseBufferQueue()**

```
virtual IpxCamErr IpxCam::Stream::ReleaseBufferQueue ( ) [pure virtual]
```

Releases the [Buffer](#) Queue.

This method releases the buffer queue of the data stream object.

**Returns**

Returns Error code

**7.17.3.13 GetBufferQueueSize()**

```
virtual size_t IpxCam::Stream::GetBufferQueueSize ( ) [pure virtual]
```

Retrieves the [Buffer](#) Queue size.

This functions returns the buffer queue size of the data stream object.

**Returns**

Returns the [Buffer](#) Queue size

**7.17.3.14 RegisterEvent()**

```
virtual IpxCamErr IpxCam::Stream::RegisterEvent (
    uint32_t eventType,
    IpxCam::EventCallback * eventCallback,
    void * pPrivate ) [pure virtual]
```

Registers the EventCallback.

This method registers the data [Stream](#) class method as a callback method to be called when event of the specified type occurs.

**Parameters**

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	event Callback function pointer
in	<i>pPrivate</i>	pointer to the user's data

**Returns**

Returns Error code

**7.17.3.15 UnRegisterEvent()**

```
virtual IpxCamErr IpxCam::Stream::UnRegisterEvent (
    uint32_t eventType,
    IpxCam::EventCallback * eventCallback,
    void * pPrivate ) [pure virtual]
```

Unregisters the EventCallback.

This method unregisters the data [Stream](#) class callback method for the specified event type

**Parameters**

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	event Callback function pointer
in	<i>pPrivate</i>	pointer to the user's data

**Returns**

Returns Error code

**7.17.3.16 GetParameters()**

```
virtual IpxGenParam::Array* IpxCam::Stream::GetParameters (
    IpxCamErr * err = nullptr ) [pure virtual]
```

Returns the GenICam parameters array.

This method returns the pointer to [IpxGenParam::Array](#) object of the GenICam parameters array for the data stream object

**Parameters**

out	err	returns the error code
-----	-----	------------------------

**Returns**

Returns the data stream GenICam parameters array

**7.17.3.17 GetNumDelivered()**

```
virtual uint64_t IpxCam::Stream::GetNumDelivered ( ) [pure virtual]
```

Returns the number of the delivered buffers.

This method returns the number of the delivered buffers since the start of the last acquisition

**Returns**

Returns the number of the delivered buffers

**7.17.3.18 GetNumUnderrun()**

```
virtual uint64_t IpxCam::Stream::GetNumUnderrun ( ) [pure virtual]
```

Returns the number under-run frames.

This method returns the number of the lost frames due to the acquisition queue being under-run.

**Returns**

Returns the number of lost frames due to queue under-run

**7.17.3.19 GetNumAnnounced()**

```
virtual size_t IpxCam::Stream::GetNumAnnounced ( ) [pure virtual]
```

Returns the number of announced buffers.

This method returns the number of announced buffers in the data stream acquisition queue

**Returns**

Returns number of announced buffers

#### 7.17.3.20 GetNumQueued()

```
virtual size_t IpxCam::Stream::GetNumQueued ( ) [pure virtual]
```

Returns the number of queued buffers.

This method returns the number of queued buffers in the data stream object acquisition queue

##### Returns

Returns the number of buffers in the input pool and the number of buffers currently being filled

#### 7.17.3.21 GetNumAwaitDelivery()

```
virtual size_t IpxCam::Stream::GetNumAwaitDelivery ( ) [pure virtual]
```

Returns the number of buffers awaiting delivery.

This method returns the number of buffers awaiting the delivery from the data stream object acquisition queue to the client application

##### Returns

Returns the number of buffers in the output buffer queue

#### 7.17.3.22 GetBufferSize()

```
virtual size_t IpxCam::Stream::GetBufferSize ( ) [pure virtual]
```

Returns the buffer size.

This method returns the buffer size of the data stream object.

##### Returns

Returns the buffer size

#### 7.17.3.23 IsGrabbing()

```
virtual bool IpxCam::Stream::IsGrabbing ( ) [pure virtual]
```

This method returns a flag indicating if the data stream is grabbing or not.

##### Returns

Flag indicating the state of the acquisition engine. If true, acquisition engine has started. Otherwise, the acquisition engine is off.

#### 7.17.3.24 GetMinNumBuffers()

```
virtual size_t IpxCam::Stream::GetMinNumBuffers ( ) [pure virtual]
```

Returns the minimum number of buffers to be announced.

This method returns the minimum number of buffers to be announced in the data stream object acquisition queue to perform the grabbing

##### Returns

Returns the minimum number of buffers to announce

#### 7.17.3.25 GetBufferAlignment()

```
virtual size_t IpxCam::Stream::GetBufferAlignment ( ) [pure virtual]
```

Returns the buffer alignment size.

This method returns the alignment size of the buffers in the stream object acquisition queue

##### Returns

Returns the alignment size in bytes of the stream buffers

The documentation for this class was generated from the following file:

- IpxCameraApi.h




## 7.18 IpxGenParam::String Class Reference

A class containing methods for [String](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::String:



### Public Member Functions

- virtual [ParamType](#) [GetType](#) ()  
*This method returns the node object [String](#) type.*
- virtual size\_t [GetMaxLength](#) (IpxCamErr \*err=nullptr)=0  
*This method gets the Maximum Length of the string.*
- virtual const char \* [GetValue](#) (size\_t \*len=nullptr, IpxCamErr \*err=nullptr)=0  
*This method gets the value of the string node.*
- virtual IpxCamErr [SetValue](#) (const char \*val)=0  
*This method sets the value of the string node.*

#### 7.18.1 Detailed Description

A class containing methods for [String](#) GenICam camera parameter.

A class containing methods to access the [String](#) GenICam camera parameter as zero-terminated array of characters

For example, the image below illustrates "DeviceModelName" parameter.

#### 7.18.2 Member Function Documentation

### 7.18.2.1 GetType()

```
virtual ParamType IpxGenParam::String::GetType ( ) [inline], [virtual]
```

This method returns the node object [String](#) type.

#### Returns

The parameter type

Implements [IpxGenParam::Param](#).

### 7.18.2.2 GetMaxLength()

```
virtual size_t IpxGenParam::String::GetMaxLength (
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the Maximum Length of the string.

#### Parameters

out	err	returns error code:
		<ul style="list-style-type: none"><li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the maximum length value</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li><li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li></ul>

#### Returns

gets the maximum length of the string

### 7.18.2.3 GetValue()

```
virtual const char* IpxGenParam::String::GetValue (
    size_t * len = nullptr,
    IpxCamErr * err = nullptr ) [pure virtual]
```

This method gets the value of the string node.

**Parameters**

out	<i>len</i>	return the length of the string
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> <li>• <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the string</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node</li> <li>• <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type</li> </ul>

**Returns**

Returns the value

**7.18.2.4 SetValue()**

```
virtual IpxCamErr IpxGenParam::String::SetValue (
    const char * val ) [pure virtual]
```

This method sets the value of the string node.

**Parameters**

in	<i>val</i>	Set the value of the string node
----	------------	----------------------------------

**Returns**

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the string
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

**7.19 IpxCam::System Class Reference**

The [System](#) class represents an abstraction of the [System](#) module of the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

## Public Member Functions

- virtual `~System ()`  
*System class Destructor.*
- virtual void `Release ()=0`  
*This method releases the instance of the system object.*
- virtual `InterfaceList * GetInterfaceList (InterfaceType type=AllInterfaces)=0`  
*This method returns the list of all the interfaces of the system object.*
- virtual `Interface * GetInterfaceById (const char *ifaceId)=0`  
*Retrieves the interface specified by interface identifier.*
- virtual const char \* `GetDisplayName ()=0`  
*Retrieves the name of the GenTL Producer.*
- virtual const char \* `GetVersion ()=0`  
*Returns the GenTL Producer version.*
- virtual `Device * CreateDeviceFromConfig (const char *fileName, IpxCamErr *err=nullptr)=0`  
*Creates the Device object from configuration file.*
- virtual `IpxCamErr RegisterGenTLProvider (const char *fileName)=0`  
*Registers the GenTL CTI library.*

### 7.19.1 Detailed Description

The `System` class represents an abstraction of the `System` module of the GenTL module hierarchy.

This class provides member functions to enumerate and instantiate the available interfaces reachable. It also provides a method for the configuration of the device module. This system module is the root of the GenTL Module hierarchy. `IpxCam::System` class has member functions to find all the interfaces, display the user readable name and producer version of the GenTL system. The `IpxCam::System` class can be used to obtain `IpxCam::InterfaceList`, then get the list `IpxCam::DeviceInfo` objects on the `IpxCam::Interface`, and create `IpxCam::Device` object, representing the camera device .

The following is an example on how to use some of the public Member Functions.

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();
IpxCam::DeviceInfo *lDeviceInfo = nullptr;

if (system)
{
    //Retrieve the System Name
    const char* displayname_str = system->GetDisplayName();
    std::cout << "DisplayName " << displayname_str;

    //Retrieve the Version of the System
    const char* version_str = system->GetVersion();
    std::cout << "Version " << system->GetVersion();

    IpxCam::Interface *iface = nullptr;
    IpxCam::Interface *iface2 = nullptr;
    std::cout << "Interfaces Available:" << endl;

    std::vector<IpxCam::Interface*> ifaceVector;

    //Get the Interface List for the System
    IpxCam::InterfaceList* list = system->GetInterfaceList();
    for(IpxCam::List<IpxCam::Interface*>::elem_type* iface = list
        ->GetFirst(); iface; iface = list->GetNext())
    {
        ifaceVector.push_back(iface);
    }
}
```

```

    //Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->
    GetDescription() << "Id " << iface->GetId() << endl;
}

//List the number of Interfaces in the System
std::cout << "Number of Interfaces in the System: " << list->GetCount() << endl;

//Example of sending Interface By Id
iface2 = system->GetInterfaceById(ifaceVector[0]->GetId());

std::cout << "Interface Description: " << iface2->GetDescription() << endl;
lDeviceInfo = iface2->GetFirstDeviceInfo();
std::cout << "ModelName" << lDeviceInfo->GetModel() << endl;

std::cout << "Releasing system" << endl;
list->Release();
system->Release();
}

```

## 7.19.2 Constructor & Destructor Documentation

### 7.19.2.1 ~System()

```
virtual IpxCam::System::~~System ( ) [inline], [virtual]
```

[System](#) class Destructor.

Destroys the [System](#) object and all its descendants. Here is the call graph for this function:



## 7.19.3 Member Function Documentation

### 7.19.3.1 Release()

```
virtual void IpxCam::System::Release ( ) [pure virtual]
```

This method releases the instance of the system object.

**Returns**

void.

The following shows an example on how to use the **Release** method to release the system object instantiated.

```
//Get the GenTL System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Add Code Here

    //Release the GenTL System
    system->Release();
}
```

**7.19.3.2 GetInterfaceList()**

```
virtual InterfaceList* IpxCam::System::GetInterfaceList (
    InterfaceType type = AllInterfaces ) [pure virtual]
```

This method returns the list of all the interfaces of the system object.

GetInterfaceList method lists all the available hardware interfaces with the transport layers technologies, supported by GenTL producer library

**Parameters**

in	type	interface type
----	------	----------------

**Returns**

Returns the interface list

The following is an example on how to use the **GetInterfaceList** method.

```
// Used later to get chosen interface
std::vector<IpxCam::Interface*> ifaceVector;

// Get the Interface List for the System
auto list = system->GetInterfaceList();

// Get the individual Interface elements
for (auto iface = list->GetFirst(); iface; iface = list->GetNext())
{
    ifaceVector.push_back(iface);

    // Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->
        GetDescription() << "Id " << iface->GetId() << endl;
}

// List has to be released
list->Release();
```

## 7.19.3.3 GetInterfaceById()

```
virtual Interface* IpxCam::System::GetInterfaceById (
    const char * ifaceId ) [pure virtual]
```

Retrieves the interface specified by interface identifier.

This method returns the interface by unique string identifier of the system object.

## Parameters

in	<i>ifaceId</i> ↔ <i>Id</i>	Interface identifier
----	-------------------------------	----------------------

## Returns

Returns the [Interface](#) or nullptr if no such interface is found

For example, the const char \*ifaceId interface identification name could be as shown below:

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

const char *ifaceId = "\\?\u
sb#vid_20f7&pid_30b3&mi_00#7&16f3afad&0&0000#{ff958afd-fce7-4264-994c-8fa230d5a524}";

auto iface = system->GetInterface(ifaceId);
```

This method will retrieve the available interface list of the system.

## 7.19.3.4 GetDisplayName()

```
virtual const char* IpxCam::System::GetDisplayName ( ) [pure virtual]
```

Retrieves the name of the GenTL Producer.

This method returns the User readable name of the GenTL Producer of the system object.

## Returns

Returns the Display Name string

The following is an example on how to use the GetDisplayName method

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Retrieve the System Name
    const char* displayname_str = system->GetDisplayName();
    std::cout << "DisplayName " << displayname_str;

    // some code here

    system->Release();
}
```

### 7.19.3.5 GetVersion()

```
virtual const char* IpxCam::System::GetVersion ( ) [pure virtual]
```

Returns the GenTL Producer version.

This method returns the version of the GenTL Producer of the system object.

#### Returns

Returns the Version string

The following is an example on how to use the GetVersion method

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Retrieve the Version of the System
    const char* version_str = system->GetVersion();
    std::cout << "Version " << system->GetVersion();

    // some code here

    system->Release();
}
```

### 7.19.3.6 CreateDeviceFromConfig()

```
virtual Device* IpxCam::System::CreateDeviceFromConfig (
    const char * fileName,
    IpxCamErr * err = nullptr ) [pure virtual]
```

Creates the [Device](#) object from configuration file.

This method creates, configures and sets up the device using the information retrieved from the specified configuration file

#### Parameters

in	<i>fileName</i>	Configuration file to open
out	<i>err</i>	returns the error code

#### Returns

Returns [Device](#) or nullptr if device cannot be instantiated



### 7.19.3.7 RegisterGenTLProvider()

```
virtual IpxCamErr IpxCam::System::RegisterGenTLProvider (
    const char * fileName ) [pure virtual]
```

Registers the GenTL CTI library.

This method registers the 3rd party GenTL provider CTI library in the [System](#).

#### Parameters

in	<i>fileName</i>	path to GenTL CTI file to add
----	-----------------	-------------------------------

#### Returns

Returns the error code

The documentation for this class was generated from the following file:

- IpxCameraApi.h



# Index

- ~Array
  - IpxGenParam::Array, [33](#)
- ~Buffer
  - IpxCam::Buffer, [50](#)
- ~Device
  - IpxCam::Device, [62](#)
- ~DeviceInfo
  - IpxCam::DeviceInfo, [69](#)
- ~IpxGenParamTreeView
  - IpxGui::IpxGenParamTreeView, [89](#)
- ~Interface
  - IpxCam::Interface, [99](#)
- ~List
  - IpxCam::List, [108](#)
- ~Param
  - IpxGenParam::Param, [112](#)
- ~Stream
  - IpxCam::Stream, [121](#)
- ~System
  - IpxCam::System, [135](#)
- AllocBufferQueue
  - IpxCam::Stream, [125](#)
- CancelBuffer
  - IpxCam::Stream, [124](#)
- clearParams
  - IpxGui::IpxGenParamTreeView, [92](#)
- CreateBuffer
  - IpxCam::Stream, [121](#)
- CreateDeviceFromConfig
  - IpxCam::Interface, [105](#)
  - IpxCam::System, [138](#)
- CreateGenParamTreeViewForArrayA
  - IpxGui, [19](#)
- CreateGenParamTreeViewForArrayW
  - IpxGui, [20](#)
- CreateGenParamTreeViewForNodemapA
  - IpxGui, [21](#)
- CreateGenParamTreeViewForNodemapW
  - IpxGui, [22](#)
- DestroyGenParamTreeView
  - IpxGui, [23](#)
- DeviceAccess
  - IpxCam, [14](#)
- DeviceInfoList
  - IpxCam, [12](#)
- DeviceList
  - IpxCam, [12](#)
- elem\_type
  - IpxCam::List, [108](#)
- Endianness
  - IpxCam::Device, [62](#)
- EventCallback
  - IpxCam, [13](#)
- EventCallback2
  - IpxCam, [13](#)
- Execute
  - IpxGenParam::Command, [58](#)
- ExecuteCommand
  - IpxGenParam::Array, [45](#)
- FlushBuffers
  - IpxCam::Stream, [124](#)
- FlushOperation
  - IpxCam, [14](#)
- ForceIP
  - IpxCam::DeviceInfo, [74](#), [75](#)
- GetAccessStatus
  - IpxCam::DeviceInfo, [72](#)
- GetBoolean
  - IpxGenParam::Array, [33](#)
- GetBooleanValue
  - IpxGenParam::Array, [39](#)
- GetBuffer
  - IpxCam::Stream, [123](#)
- GetBufferAlignment
  - IpxCam::Stream, [130](#)
- GetBufferPtr
  - IpxCam::Buffer, [50](#)
- GetBufferQueueSize
  - IpxCam::Stream, [126](#)
- GetBufferSize
  - IpxCam::Buffer, [51](#)
  - IpxCam::Stream, [129](#)
- GetCameraParameters
  - IpxCam::Device, [67](#)
- GetCommand
  - IpxGenParam::Array, [34](#)

- GetCount
  - IpxCam::List, [109](#)
  - IpxGenParam::Array, [38](#)
  - IpxGenParam::Category, [56](#)
- GetDeliveredHeight
  - IpxCam::Buffer, [54](#)
- GetDescription
  - IpxCam::Interface, [102](#)
  - IpxGenParam::Param, [113](#)
- GetDeviceInfoById
  - IpxCam::Interface, [101](#)
- GetDeviceInfoList
  - IpxCam::Interface, [100](#)
- GetDisplayName
  - IpxCam::DeviceInfo, [71](#)
  - IpxCam::System, [137](#)
  - IpxGenParam::Param, [113](#)
- GetEndianness
  - IpxCam::Device, [68](#)
- GetEnum
  - IpxGenParam::Array, [35](#)
- GetEnumEntriesCount
  - IpxGenParam::Enum, [77](#)
- GetEnumEntryByIndex
  - IpxGenParam::Enum, [77](#)
- GetEnumEntryByName
  - IpxGenParam::Enum, [79](#)
- GetEnumEntryByValue
  - IpxGenParam::Enum, [79](#)
- GetEnumValue
  - IpxGenParam::Array, [41](#)
- GetEnumValueStr
  - IpxGenParam::Array, [40](#)
- GetFirst
  - IpxCam::List, [109](#)
- GetFirstDeviceInfo
  - IpxCam::Interface, [100](#)
- GetFloat
  - IpxGenParam::Array, [35](#)
- GetFloatValue
  - IpxGenParam::Array, [42](#)
- GetFrameID
  - IpxCam::Buffer, [52](#)
- GetHeight
  - IpxCam::Buffer, [53](#)
- GetIPAddress
  - IpxCam::DeviceInfo, [72](#)
- GetIPGateway
  - IpxCam::DeviceInfo, [73](#)
- GetIPMask
  - IpxCam::DeviceInfo, [73](#)
- GetID
  - IpxCam::DeviceInfo, [70](#)
- GetId
  - IpxCam::Interface, [102](#)
- GetImage
  - IpxCam::Buffer, [50](#)
- GetImageOffset
  - IpxCam::Buffer, [50](#)
- GetIncrement
  - IpxGenParam::Int, [98](#)
- GetInfo
  - IpxCam::Device, [63](#)
- GetInt
  - IpxGenParam::Array, [36](#)
- GetIntegerValue
  - IpxGenParam::Array, [43](#)
- GetInterface
  - IpxCam::DeviceInfo, [70](#)
- GetInterfaceById
  - IpxCam::System, [136](#)
- GetInterfaceList
  - IpxCam::System, [136](#)
- GetIP
  - IpxCam::DeviceInfo, [74](#)
- GetMax
  - IpxGenParam::Float, [87](#)
  - IpxGenParam::Int, [97](#)
- GetMaxLength
  - IpxGenParam::String, [132](#)
- GetMin
  - IpxGenParam::Float, [86](#)
  - IpxGenParam::Int, [97](#)
- GetMinNumBuffers
  - IpxCam::Stream, [130](#)
- GetModel
  - IpxCam::DeviceInfo, [70](#)
- GetName
  - IpxGenParam::Param, [112](#)
- GetNext
  - IpxCam::List, [109](#)
- GetNode
  - IpxGenParam::Param, [116](#)
- GetNodeMap
  - IpxGenParam::Array, [37](#)
- GetNumAnnounced
  - IpxCam::Stream, [128](#)
- GetNumAwaitDelivery
  - IpxCam::Stream, [129](#)
- GetNumDelivered
  - IpxCam::Stream, [128](#)
- GetNumQueued
  - IpxCam::Stream, [128](#)
- GetNumStreams
  - IpxCam::Device, [62](#)
- GetNumUnderrun
  - IpxCam::Stream, [128](#)
- GetParam

- [IpxGenParam::Array](#), [33](#)
- [GetParamByIndex](#)
  - [IpxGenParam::Array](#), [38](#)
  - [IpxGenParam::Category](#), [56](#)
- [GetParameters](#)
  - [IpxCam::Interface](#), [105](#)
  - [IpxCam::Stream](#), [127](#)
- [GetPixelFormat](#)
  - [IpxCam::Buffer](#), [51](#)
- [getPollingTime](#)
  - [IpxGui::IpxGenParamTreeView](#), [94](#)
- [GetRootCategory](#)
  - [IpxGenParam::Array](#), [37](#)
- [GetSerialNumber](#)
  - [IpxCam::DeviceInfo](#), [71](#)
- [GetStreamById](#)
  - [IpxCam::Device](#), [63](#)
- [GetStreamByIndex](#)
  - [IpxCam::Device](#), [62](#)
- [GetString](#)
  - [IpxGenParam::Array](#), [36](#)
- [GetStringValue](#)
  - [IpxGenParam::Array](#), [44](#)
- [GetTimestamp](#)
  - [IpxCam::Buffer](#), [51](#)
- [GetToolTip](#)
  - [IpxGenParam::Param](#), [112](#)
- [GetTransportParameters](#)
  - [IpxCam::Device](#), [66](#)
- [GetType](#)
  - [IpxCam::Interface](#), [102](#)
  - [IpxGenParam::Boolean](#), [47](#)
  - [IpxGenParam::Category](#), [56](#)
  - [IpxGenParam::Command](#), [58](#)
  - [IpxGenParam::Enum](#), [77](#)
  - [IpxGenParam::EnumEntry](#), [82](#)
  - [IpxGenParam::Float](#), [85](#)
  - [IpxGenParam::Int](#), [96](#)
  - [IpxGenParam::Param](#), [112](#)
  - [IpxGenParam::String](#), [131](#)
- [GetUSB3HostInfo](#)
  - [IpxCam::DeviceInfo](#), [72](#)
- [GetUnit](#)
  - [IpxGenParam::Float](#), [87](#)
- [GetUserDefinedName](#)
  - [IpxCam::DeviceInfo](#), [71](#)
- [GetUserPtr](#)
  - [IpxCam::Buffer](#), [51](#)
- [GetValue](#)
  - [IpxGenParam::Boolean](#), [48](#)
  - [IpxGenParam::Enum](#), [79](#)
  - [IpxGenParam::EnumEntry](#), [83](#)
  - [IpxGenParam::Float](#), [86](#)
  - [IpxGenParam::Int](#), [96](#)
  - [IpxGenParam::String](#), [132](#)
- [GetValueStr](#)
  - [IpxGenParam::Enum](#), [80](#)
  - [IpxGenParam::EnumEntry](#), [83](#)
- [GetVendor](#)
  - [IpxCam::DeviceInfo](#), [70](#)
- [GetVersion](#)
  - [IpxCam::DeviceInfo](#), [71](#)
  - [IpxCam::Interface](#), [103](#)
  - [IpxCam::System](#), [137](#)
- [GetVisibility](#)
  - [IpxGenParam::Param](#), [113](#)
- [GetWidth](#)
  - [IpxCam::Buffer](#), [52](#)
- [GetXOffset](#)
  - [IpxCam::Buffer](#), [53](#)
- [GetXPadding](#)
  - [IpxCam::Buffer](#), [54](#)
- [GetYOffset](#)
  - [IpxCam::Buffer](#), [53](#)
- [GetYPadding](#)
  - [IpxCam::Buffer](#), [54](#)
- [InterfaceList](#)
  - [IpxCam](#), [12](#)
- [InterfaceType](#)
  - [IpxCam](#), [13](#)
- [IpxCam](#), [11](#)
  - [DeviceAccess](#), [14](#)
  - [DeviceInfoList](#), [12](#)
  - [DeviceList](#), [12](#)
  - [EventCallback](#), [13](#)
  - [EventCallback2](#), [13](#)
  - [FlushOperation](#), [14](#)
  - [InterfaceList](#), [12](#)
  - [InterfaceType](#), [13](#)
  - [IpxCam\\_GetSystem](#), [14](#)
- [IpxCam::Buffer](#), [48](#)
  - [~Buffer](#), [50](#)
  - [GetBufferPtr](#), [50](#)
  - [GetBufferSize](#), [51](#)
  - [GetDeliveredHeight](#), [54](#)
  - [GetFrameID](#), [52](#)
  - [GetHeight](#), [53](#)
  - [GetImage](#), [50](#)
  - [GetImageOffset](#), [50](#)
  - [GetPixelFormat](#), [51](#)
  - [GetTimestamp](#), [51](#)
  - [GetUserPtr](#), [51](#)
  - [GetWidth](#), [52](#)
  - [GetXOffset](#), [53](#)
  - [GetXPadding](#), [54](#)
  - [GetYOffset](#), [53](#)
  - [GetYPadding](#), [54](#)

- IsIncomplete, [52](#)
- IsKacFrameB, [54](#)
- IpxCam::Device, [59](#)
  - ~Device, [62](#)
  - Endianness, [62](#)
  - GetCameraParameters, [67](#)
  - GetEndianness, [68](#)
  - GetInfo, [63](#)
  - GetNumStreams, [62](#)
  - GetStreamById, [63](#)
  - GetStreamByIndex, [62](#)
  - GetTransportParameters, [66](#)
  - LoadConfiguration, [67](#)
  - ReadMem, [63](#)
  - RegisterEvent, [65](#)
  - RegisterEvent2, [64](#)
  - SaveConfiguration, [67](#)
  - UnRegisterEvent, [66](#)
  - UnRegisterEvent2, [65](#)
  - UploadEventType, [60](#)
  - WriteMem, [64](#)
- IpxCam::DeviceInfo, [68](#)
  - ~DeviceInfo, [69](#)
  - ForceIP, [74, 75](#)
  - GetAccessStatus, [72](#)
  - GetDisplayName, [71](#)
  - GetIPAddress, [72](#)
  - GetIPGateway, [73](#)
  - GetIPMask, [73](#)
  - GetID, [70](#)
  - GetInterface, [70](#)
  - GetIP, [74](#)
  - GetModel, [70](#)
  - GetSerialNumber, [71](#)
  - GetUSB3HostInfo, [72](#)
  - GetUserDefinedName, [71](#)
  - GetVendor, [70](#)
  - GetVersion, [71](#)
- IpxCam::Interface, [98](#)
  - ~Interface, [99](#)
  - CreateDeviceFromConfig, [105](#)
  - GetDescription, [102](#)
  - GetDeviceInfoById, [101](#)
  - GetDeviceInfoList, [100](#)
  - GetFirstDeviceInfo, [100](#)
  - GetId, [102](#)
  - GetParameters, [105](#)
  - GetType, [102](#)
  - GetVersion, [103](#)
  - ReEnumerateDevices, [101](#)
  - RegisterEvent, [104](#)
  - RegisterEvent2, [103](#)
  - UnRegisterEvent, [104](#)
  - UnRegisterEvent2, [104](#)
- IpxCam::List
  - ~List, [108](#)
  - elem\_type, [108](#)
  - GetCount, [109](#)
  - GetFirst, [109](#)
  - GetNext, [109](#)
  - Release, [108](#)
- IpxCam::List<\_T>, [106](#)
- IpxCam::Stream, [119](#)
  - ~Stream, [121](#)
  - AllocBufferQueue, [125](#)
  - CancelBuffer, [124](#)
  - CreateBuffer, [121](#)
  - FlushBuffers, [124](#)
  - GetBuffer, [123](#)
  - GetBufferAlignment, [130](#)
  - GetBufferQueueSize, [126](#)
  - GetBufferSize, [129](#)
  - GetMinNumBuffers, [130](#)
  - GetNumAnnounced, [128](#)
  - GetNumAwaitDelivery, [129](#)
  - GetNumDelivered, [128](#)
  - GetNumQueued, [128](#)
  - GetNumUnderrun, [128](#)
  - GetParameters, [127](#)
  - IsGrabbing, [129](#)
  - QueueBuffer, [123](#)
  - RegisterEvent, [126](#)
  - Release, [121](#)
  - ReleaseBufferQueue, [126](#)
  - RevokeBuffer, [122](#)
  - SetBuffer, [122](#)
  - StartAcquisition, [124](#)
  - StopAcquisition, [125](#)
  - UnRegisterEvent, [127](#)
- IpxCam::System, [133](#)
  - ~System, [135](#)
  - CreateDeviceFromConfig, [138](#)
  - GetDisplayName, [137](#)
  - GetInterfaceById, [136](#)
  - GetInterfaceList, [136](#)
  - GetVersion, [137](#)
  - RegisterGenTLProvider, [138](#)
  - Release, [135](#)
- IpxCam\_GetSystem
  - IpxCam, [14](#)
- IpxGenParam, [15](#)
  - Namespace, [17](#)
  - ParamType, [16](#)
  - Visibility, [17](#)
- IpxGenParam::Array, [31](#)
  - ~Array, [33](#)
  - ExecuteCommand, [45](#)
  - GetBoolean, [33](#)

- GetBooleanValue, [39](#)
- GetCommand, [34](#)
- GetCount, [38](#)
- GetEnum, [35](#)
- GetEnumValue, [41](#)
- GetEnumValueStr, [40](#)
- GetFloat, [35](#)
- GetFloatValue, [42](#)
- GetInt, [36](#)
- GetIntegerValue, [43](#)
- GetNodeMap, [37](#)
- GetParam, [33](#)
- GetParamByIndex, [38](#)
- GetRootCategory, [37](#)
- GetString, [36](#)
- GetStringValue, [44](#)
- IsCommandDone, [45](#)
- Poll, [46](#)
- SetBooleanValue, [38](#)
- SetEnumValue, [40](#)
- SetEnumValueStr, [39](#)
- SetFloatValue, [41](#)
- SetIntegerValue, [42](#)
- SetStringValue, [44](#)
- IpxGenParam::Boolean, [46](#)
  - GetType, [47](#)
  - GetValue, [48](#)
  - SetValue, [47](#)
- IpxGenParam::Category, [55](#)
  - GetCount, [56](#)
  - GetParamByIndex, [56](#)
  - GetType, [56](#)
- IpxGenParam::Command, [57](#)
  - Execute, [58](#)
  - GetType, [58](#)
  - IsDone, [58](#)
- IpxGenParam::Enum, [75](#)
  - GetEnumEntriesCount, [77](#)
  - GetEnumEntryByIndex, [77](#)
  - GetEnumEntryByName, [79](#)
  - GetEnumEntryByValue, [79](#)
  - GetType, [77](#)
  - GetValue, [79](#)
  - GetValueStr, [80](#)
  - SetValue, [80](#)
  - SetValueStr, [81](#)
- IpxGenParam::EnumEntry, [81](#)
  - GetType, [82](#)
  - GetValue, [83](#)
  - GetValueStr, [83](#)
- IpxGenParam::Float, [84](#)
  - GetMax, [87](#)
  - GetMin, [86](#)
  - GetType, [85](#)
- GetUnit, [87](#)
- GetValue, [86](#)
- SetValue, [85](#)
- IpxGenParam::Int, [95](#)
  - GetIncrement, [98](#)
  - GetMax, [97](#)
  - GetMin, [97](#)
  - GetType, [96](#)
  - GetValue, [96](#)
  - SetValue, [96](#)
- IpxGenParam::Param, [110](#)
  - ~Param, [112](#)
  - GetDescription, [113](#)
  - GetDisplayName, [113](#)
  - GetName, [112](#)
  - GetNode, [116](#)
  - GetToolTip, [112](#)
  - GetType, [112](#)
  - GetVisibility, [113](#)
  - IsAvailable, [114](#)
  - IsReadable, [114](#)
  - IsStreamable, [114](#)
  - IsValueCached, [113](#)
  - IsVisible, [115](#)
  - IsWritable, [114](#)
  - RegisterEventSink, [115](#)
  - ToBoolean, [116](#)
  - ToCategory, [116](#)
  - ToCommand, [117](#)
  - ToEnum, [117](#)
  - ToEnumEntry, [117](#)
  - ToFloat, [117](#)
  - ToInt, [118](#)
  - ToString, [118](#)
  - UnregisterEventSink, [115](#)
- IpxGenParam::ParamEventSink, [118](#)
  - OnParameterUpdate, [119](#)
- IpxGenParam::String, [131](#)
  - GetMaxLength, [132](#)
  - GetType, [131](#)
  - GetValue, [132](#)
  - SetValue, [133](#)
- IpxGui, [17](#)
  - CreateGenParamTreeViewForArrayA, [19](#)
  - CreateGenParamTreeViewForArrayW, [20](#)
  - CreateGenParamTreeViewForNodemapA, [21](#)
  - CreateGenParamTreeViewForNodemapW, [22](#)
  - DestroyGenParamTreeView, [23](#)
  - SelectCameraA, [23](#)
  - SelectCameraW, [24](#)
  - ShowCamConfigDialog, [25](#)
  - ShowColorDialog, [29](#)
  - ShowFrameABDialog, [26](#)
  - ShowOutputDialog, [28](#)

- ShowPulseDialog, [27](#)
  - ShowStrobeDialog, [27](#)
  - ShowTriggerDialog, [26](#)
  - Visibility, [19](#)
- IpxGui::IpxGenParamTreeView, [88](#)
  - ~IpxGenParamTreeView, [89](#)
  - clearParams, [92](#)
  - getPollingTime, [94](#)
  - loadState, [93](#)
  - saveState, [93](#)
  - setParams, [90](#), [91](#)
  - setPollingTime, [94](#)
  - setVisibility, [92](#)
  - visibility, [92](#)
- IsAvailable
  - IpxGenParam::Param, [114](#)
- IsCommandDone
  - IpxGenParam::Array, [45](#)
- IsDone
  - IpxGenParam::Command, [58](#)
- IsGrabbing
  - IpxCam::Stream, [129](#)
- IsIncomplete
  - IpxCam::Buffer, [52](#)
- IsKacFrameB
  - IpxCam::Buffer, [54](#)
- IsReadable
  - IpxGenParam::Param, [114](#)
- IsStreamable
  - IpxGenParam::Param, [114](#)
- IsValueCached
  - IpxGenParam::Param, [113](#)
- IsVisible
  - IpxGenParam::Param, [115](#)
- IsWritable
  - IpxGenParam::Param, [114](#)
- LoadConfiguration
  - IpxCam::Device, [67](#)
- loadState
  - IpxGui::IpxGenParamTreeView, [93](#)
- Namespace
  - IpxGenParam, [17](#)
- OnParameterUpdate
  - IpxGenParam::ParamEventSink, [119](#)
- ParamType
  - IpxGenParam, [16](#)
- Poll
  - IpxGenParam::Array, [46](#)
- QueueBuffer
  - IpxCam::Stream, [123](#)
- ReEnumerateDevices
  - IpxCam::Interface, [101](#)
- ReadMem
  - IpxCam::Device, [63](#)
- RegisterEvent
  - IpxCam::Device, [65](#)
  - IpxCam::Interface, [104](#)
  - IpxCam::Stream, [126](#)
- RegisterEvent2
  - IpxCam::Device, [64](#)
  - IpxCam::Interface, [103](#)
- RegisterEventSink
  - IpxGenParam::Param, [115](#)
- RegisterGenTLProvider
  - IpxCam::System, [138](#)
- Release
  - IpxCam::List, [108](#)
  - IpxCam::Stream, [121](#)
  - IpxCam::System, [135](#)
- ReleaseBufferQueue
  - IpxCam::Stream, [126](#)
- RevokeBuffer
  - IpxCam::Stream, [122](#)
- SaveConfiguration
  - IpxCam::Device, [67](#)
- saveState
  - IpxGui::IpxGenParamTreeView, [93](#)
- SelectCameraA
  - IpxGui, [23](#)
- SelectCameraW
  - IpxGui, [24](#)
- SetBooleanValue
  - IpxGenParam::Array, [38](#)
- SetBuffer
  - IpxCam::Stream, [122](#)
- SetEnumValue
  - IpxGenParam::Array, [40](#)
- SetEnumValueStr
  - IpxGenParam::Array, [39](#)
- SetFloatValue
  - IpxGenParam::Array, [41](#)
- SetIntegerValue
  - IpxGenParam::Array, [42](#)
- setParams
  - IpxGui::IpxGenParamTreeView, [90](#), [91](#)
- setPollingTime
  - IpxGui::IpxGenParamTreeView, [94](#)
- SetStringValue
  - IpxGenParam::Array, [44](#)
- SetValue
  - IpxGenParam::Boolean, [47](#)
  - IpxGenParam::Enum, [80](#)
  - IpxGenParam::Float, [85](#)



- [IpxGenParam::Int, 96](#)
  - [IpxGenParam::String, 133](#)
- [SetValueStr](#)
  - [IpxGenParam::Enum, 81](#)
- [setVisibility](#)
  - [IpxGui::IpxGenParamTreeView, 92](#)
- [ShowCamConfigDialog](#)
  - [IpxGui, 25](#)
- [ShowColorDialog](#)
  - [IpxGui, 29](#)
- [ShowFrameABDialog](#)
  - [IpxGui, 26](#)
- [ShowOutputDialog](#)
  - [IpxGui, 28](#)
- [ShowPulseDialog](#)
  - [IpxGui, 27](#)
- [ShowStrobeDialog](#)
  - [IpxGui, 27](#)
- [ShowTriggerDialog](#)
  - [IpxGui, 26](#)
- [StartAcquisition](#)
  - [IpxCam::Stream, 124](#)
- [StopAcquisition](#)
  - [IpxCam::Stream, 125](#)
- [ToBoolean](#)
  - [IpxGenParam::Param, 116](#)
- [ToCategory](#)
  - [IpxGenParam::Param, 116](#)
- [ToCommand](#)
  - [IpxGenParam::Param, 117](#)
- [ToEnum](#)
  - [IpxGenParam::Param, 117](#)
- [ToEnumEntry](#)
  - [IpxGenParam::Param, 117](#)
- [ToFloat](#)
  - [IpxGenParam::Param, 117](#)
- [ToInt](#)
  - [IpxGenParam::Param, 118](#)
- [ToString](#)
  - [IpxGenParam::Param, 118](#)
- [UnRegisterEvent](#)
  - [IpxCam::Device, 66](#)
  - [IpxCam::Interface, 104](#)
  - [IpxCam::Stream, 127](#)
- [UnRegisterEvent2](#)
  - [IpxCam::Device, 65](#)
  - [IpxCam::Interface, 104](#)
- [UnregisterEventSink](#)
  - [IpxGenParam::Param, 115](#)
- [UploadEventType](#)
  - [IpxCam::Device, 60](#)
- [Visibility](#)
  - [IpxGenParam, 17](#)
  - [IpxGui, 19](#)
  - [visibility](#)
    - [IpxGui::IpxGenParamTreeView, 92](#)
  - [WriteMem](#)
    - [IpxCam::Device, 64](#)