

Imperx Camera SDK

1.5.0.56

Generated by Doxygen 1.8.11

Contents

1	Imperx Camera C++ SDK	1
1.1	General Information	1
1.2	lpxCameraApi library	1
1.2.1	lpxCam namespace	1
1.2.2	lpxGenParam namespace	2
1.3	lpxCameraGuiApi library	2
2	Deprecated List	3
3	Namespace Index	5
3.1	Namespace List	5
4	Hierarchical Index	7
4.1	Class Hierarchy	7
5	Class Index	9
5.1	Class List	9

6 Namespace Documentation	11
6.1 IpxCam Namespace Reference	11
6.1.1 Detailed Description	12
6.1.2 Typedef Documentation	12
6.1.2.1 InterfaceList	12
6.1.2.2 DeviceInfoList	12
6.1.2.3 DeviceList	12
6.1.2.4 EventCallback	12
6.1.2.5 EventCallback2	13
6.1.3 Enumeration Type Documentation	13
6.1.3.1 InterfaceType	13
6.1.3.2 FlushOperation	13
6.1.3.3 DeviceAccess	13
6.1.4 Function Documentation	14
6.1.4.1 IpxCam_GetSystem()	14
6.2 IpxGenParam Namespace Reference	14
6.2.1 Detailed Description	15
6.2.2 Enumeration Type Documentation	15
6.2.2.1 ParamType	15
6.2.2.2 NameSpace	15
6.2.2.3 Visibility	16
6.3 IpxGui Namespace Reference	16
6.3.1 Detailed Description	17
6.3.2 Enumeration Type Documentation	17
6.3.2.1 Visibility	17
6.3.3 Function Documentation	18
6.3.3.1 CreateGenParamTreeViewForArrayA(IpxGenParam::Array *genParam, const char *title, uintptr_t parentWindow=0)	18

6.3.3.2	CreateGenParamTreeViewForArrayW(IpxGenParam::Array *genParam, const wchar_t *title, uintptr_t parentWindow=0)	18
6.3.3.3	CreateGenParamTreeViewForNodemapA(IPX_GENAPI_NS::INodeMap *nodemap, const char *title, uintptr_t parentWindow=0)	19
6.3.3.4	CreateGenParamTreeViewForNodemapW(IPX_GENAPI_NS::INodeMap *nodemap, const wchar_t *title, uintptr_t parentWindow=0)	20
6.3.3.5	DestroyGenParamTreeView(IpxGenParamTreeView *view)	20
6.3.3.6	SelectCameraA(IpxCam::System *pSystem, const char *title, uintptr_t parentWindow=0, bool poll=true)	21
6.3.3.7	SelectCameraW(IpxCam::System *pSystem, const wchar_t *title, uintptr_t parentWindow=0, bool poll=true)	22
6.3.3.8	ShowCamConfigDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	22
6.3.3.9	ShowFrameABDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	23
6.3.3.10	ShowTriggerDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	23
6.3.3.11	ShowPulseDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	24
6.3.3.12	ShowStrobeDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	24
6.3.3.13	ShowOutputDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	25
6.3.3.14	ShowColorDialog(IpxCam::Device *device, uintptr_t parentWindow=0)	25
7	Class Documentation	27
7.1	IpxGenParam::Array Class Reference	27
7.1.1	Detailed Description	28
7.1.2	Constructor & Destructor Documentation	29
7.1.2.1	~Array()	29
7.1.3	Member Function Documentation	29
7.1.3.1	GetParam(const char *name, IpxCamErr *err)=0	29
7.1.3.2	GetBoolean(const char *name, IpxCamErr *err)=0	29
7.1.3.3	GetCommand(const char *name, IpxCamErr *err)=0	30
7.1.3.4	GetEnum(const char *name, IpxCamErr *err)=0	30
7.1.3.5	GetFloat(const char *name, IpxCamErr *err)=0	31
7.1.3.6	GetInt(const char *name, IpxCamErr *err)=0	31

7.1.3.7	GetString(const char *name, lpxCamErr *err)=0	31
7.1.3.8	GetRootCategory(lpxCamErr *err)=0	32
7.1.3.9	GetNodeMap(lpxCamErr *err)=0	32
7.1.3.10	GetCount()=0	33
7.1.3.11	GetParamByIndex(uint32_t idx, lpxCamErr *err)=0	33
7.1.3.12	SetBooleanValue(const char *name, bool aValue)=0	33
7.1.3.13	GetBooleanValue(const char *name, lpxCamErr *err=nullptr)=0	34
7.1.3.14	SetEnumValueStr(const char *name, const char *val)=0	34
7.1.3.15	SetEnumValue(const char *name, int64_t val)=0	34
7.1.3.16	GetEnumValueStr(const char *name, lpxCamErr *err=nullptr)=0	35
7.1.3.17	GetEnumValue(const char *name, lpxCamErr *err=nullptr)=0	35
7.1.3.18	SetFloatValue(const char *name, double val)=0	36
7.1.3.19	GetFloatValue(const char *name, lpxCamErr *err=nullptr)=0	36
7.1.3.20	SetIntegerValue(const char *name, int64_t val)=0	37
7.1.3.21	GetIntegerValue(const char *name, lpxCamErr *err=nullptr)=0	37
7.1.3.22	SetStringValue(const char *name, const char *val)=0	38
7.1.3.23	GetStringValue(const char *name, lpxCamErr *err=nullptr)=0	38
7.1.3.24	ExecuteCommand(const char *name)=0	38
7.1.3.25	IsCommandDone(const char *name, lpxCamErr *err=nullptr)=0	39
7.1.3.26	Poll(int64_t elapsedTime)=0	39
7.2	lpxGenParam::Boolean Class Reference	40
7.2.1	Detailed Description	40
7.2.2	Member Function Documentation	41
7.2.2.1	GetType()	41
7.2.2.2	SetValue(bool val)=0	41
7.2.2.3	GetValue(lpxCamErr *err=nullptr)=0	41
7.3	lpxCam::Buffer Class Reference	42
7.3.1	Detailed Description	43

7.3.2	Constructor & Destructor Documentation	43
7.3.2.1	~Buffer()	43
7.3.3	Member Function Documentation	43
7.3.3.1	GetImage()=0	43
7.3.3.2	GetBufferPtr()=0	44
7.3.3.3	GetImageOffset()=0	44
7.3.3.4	GetBufferSize()=0	44
7.3.3.5	GetPixelFormat()=0	44
7.3.3.6	GetUserPtr()=0	44
7.3.3.7	GetTimestamp()=0	45
7.3.3.8	GetFrameID()=0	45
7.3.3.9	IsIncomplete()=0	45
7.3.3.10	GetWidth()=0	45
7.3.3.11	GetHeight()=0	46
7.3.3.12	GetXOffset()=0	46
7.3.3.13	GetYOffset()=0	46
7.3.3.14	GetXPadding()=0	46
7.3.3.15	GetYPadding()=0	47
7.3.3.16	GetDeliveredHeight()=0	47
7.3.3.17	IsKacFrameB()=0	47
7.4	IpxGenParam::Category Class Reference	47
7.4.1	Detailed Description	48
7.4.2	Member Function Documentation	48
7.4.2.1	GetType()	48
7.4.2.2	GetCount()=0	48
7.4.2.3	GetParamByIndex(uint32_t idx, IpxCamErr *err)=0	48
7.5	IpxGenParam::Command Class Reference	49
7.5.1	Detailed Description	50

7.5.2	Member Function Documentation	50
7.5.2.1	GetType()	50
7.5.2.2	Execute()=0	50
7.5.2.3	IsDone(IpxCamErr *err=NULLPTR)=0	50
7.6	IpxCam::Device Class Reference	51
7.6.1	Detailed Description	52
7.6.2	Member Enumeration Documentation	52
7.6.2.1	UploadEventType	52
7.6.2.2	Endianness	52
7.6.3	Constructor & Destructor Documentation	53
7.6.3.1	~Device()	53
7.6.4	Member Function Documentation	53
7.6.4.1	GetNumStreams()=0	53
7.6.4.2	GetStreamByIndex(uint32_t idx=0)=0	53
7.6.4.3	GetStreamById(const char *id)=0	53
7.6.4.4	GetInfo()=0	54
7.6.4.5	ReadMem(uint64_t addr, void *data, size_t len)=0	54
7.6.4.6	WriteMem(uint64_t addr, const void *data, size_t len, size_t *written)=0	54
7.6.4.7	RegisterEvent2(uint32_t eventType, IpxCam::EventCallback2 *eventCallback, void *pPrivate)=0	54
7.6.4.8	RegisterEvent(uint32_t eventType, IpxCam::EventCallback *eventCallback, void *pPrivate)=0	55
7.6.4.9	UnRegisterEvent2(uint32_t eventType, IpxCam::EventCallback2 *eventCallback, void *pPrivate)=0	55
7.6.4.10	UnRegisterEvent(uint32_t eventType, IpxCam::EventCallback *eventCallback, void *pPrivate)=0	56
7.6.4.11	GetTransportParameters(IpxCamErr *err=NULLPTR)=0	56
7.6.4.12	GetCameraParameters(IpxCamErr *err=NULLPTR)=0	56
7.6.4.13	SaveConfiguration(const char *fileName)=0	56
7.6.4.14	LoadConfiguration(const char *fileName)=0	57

7.6.4.15	GetEndianness() const =0	57
7.7	IpxCam::DeviceInfo Class Reference	57
7.7.1	Detailed Description	58
7.7.2	Constructor & Destructor Documentation	59
7.7.2.1	~DeviceInfo()	59
7.7.3	Member Function Documentation	59
7.7.3.1	GetInterface()=0	59
7.7.3.2	GetID()=0	59
7.7.3.3	GetVendor()=0	59
7.7.3.4	GetModel()=0	59
7.7.3.5	GetDisplayName()=0	60
7.7.3.6	GetUserDefinedName()=0	60
7.7.3.7	GetSerialNumber()=0	60
7.7.3.8	GetVersion()=0	60
7.7.3.9	GetAccessStatus()=0	60
7.7.3.10	GetUSB3HostInfo()=0	61
7.7.3.11	GetIPAddress(IpxCamErr *err)=0	61
7.7.3.12	GetIPMask(IpxCamErr *err)=0	61
7.7.3.13	GetIPGateway(IpxCamErr *err)=0	61
7.7.3.14	GetIP(uint32_t *addr, uint32_t *netmask, uint32_t *gateway)=0	62
7.7.3.15	ForceIP(const char *addr, const char *netmask, const char *gateway)=0	62
7.7.3.16	ForceIP(uint32_t addr, uint32_t netmask, uint32_t gateway)=0	63
7.8	IpxGenParam::Enum Class Reference	63
7.8.1	Detailed Description	64
7.8.2	Member Function Documentation	64
7.8.2.1	GetType()	64
7.8.2.2	GetEnumEntriesCount(IpxCamErr *err=nullptr)=0	64
7.8.2.3	GetEnumEntryByIndex(size_t aIndex)=0	65

7.8.2.4	GetEnumEntryByName(const char *name)=0	65
7.8.2.5	GetEnumEntryByValue(int64_t val)=0	65
7.8.2.6	GetValue(IpxCamErr *err=nullptr)=0	66
7.8.2.7	GetValueStr(IpxCamErr *err=nullptr)=0	66
7.8.2.8	SetValue(int64_t val)=0	67
7.8.2.9	SetValueStr(const char *val)=0	67
7.9	IpxGenParam::EnumEntry Class Reference	67
7.9.1	Detailed Description	68
7.9.2	Member Function Documentation	68
7.9.2.1	GetType()	68
7.9.2.2	GetValue(IpxCamErr *err=nullptr)=0	68
7.9.2.3	GetValueStr(IpxCamErr *err=nullptr)=0	69
7.10	IpxGenParam::Float Class Reference	69
7.10.1	Detailed Description	70
7.10.2	Member Function Documentation	70
7.10.2.1	GetType()	70
7.10.2.2	SetValue(double val)=0	71
7.10.2.3	GetValue(IpxCamErr *err=nullptr)=0	71
7.10.2.4	GetMin(IpxCamErr *err=nullptr)=0	71
7.10.2.5	GetMax(IpxCamErr *err=nullptr)=0	72
7.10.2.6	GetUnit(IpxCamErr *err=nullptr)=0	72
7.11	IpxGui::IpxGenParamTreeView Class Reference	73
7.11.1	Detailed Description	74
7.11.2	Constructor & Destructor Documentation	74
7.11.2.1	~IpxGenParamTreeView()	74
7.11.3	Member Function Documentation	75
7.11.3.1	setParams(IpxGenParam::Array *genParam)=0	75
7.11.3.2	setParams(IPX_GENAPI_NS::INodeMap *nodemap)=0	76

7.11.3.3	<code>clearParams()</code> =0	77
7.11.3.4	<code>visibility()</code> const =0	77
7.11.3.5	<code>setVisibility(Visibility visibility)</code> =0	77
7.11.3.6	<code>saveState()</code> const =0	78
7.11.3.7	<code>loadState(const char *state)</code> =0	78
7.11.3.8	<code>setPollingTime(uint64_t pollingTime)</code> =0	78
7.11.3.9	<code>getPollingTime()</code> =0	78
7.12	<code>IpxGenParam::Int</code> Class Reference	79
7.12.1	Detailed Description	79
7.12.2	Member Function Documentation	80
7.12.2.1	<code>GetType()</code>	80
7.12.2.2	<code>SetValue(int64_t val)</code> =0	80
7.12.2.3	<code>GetValue(IpxCamErr *err=nullptr)</code> =0	80
7.12.2.4	<code>GetMin(IpxCamErr *err=nullptr)</code> =0	81
7.12.2.5	<code>GetMax(IpxCamErr *err=nullptr)</code> =0	81
7.12.2.6	<code>GetIncrement(IpxCamErr *err=nullptr)</code> =0	81
7.13	<code>IpxCam::Interface</code> Class Reference	82
7.13.1	Detailed Description	83
7.13.2	Constructor & Destructor Documentation	83
7.13.2.1	<code>~Interface()</code>	83
7.13.3	Member Function Documentation	83
7.13.3.1	<code>GetDeviceInfoList()</code> =0	83
7.13.3.2	<code>GetFirstDeviceInfo()</code> =0	84
7.13.3.3	<code>GetDeviceInfoById(const char *deviceId)</code> =0	84
7.13.3.4	<code>ReEnumerateDevices(bool *pChanged, uint64_t iTimeout)</code> =0	85
7.13.3.5	<code>GetDescription()</code> =0	85
7.13.3.6	<code>GetType()</code> =0	85
7.13.3.7	<code>GetId()</code> =0	86

7.13.3.8	GetVersion()=0	86
7.13.3.9	RegisterEvent2(uint32_t eventType, lpxCam::EventCallback2 *eventCallback, void *pPrivate)=0	86
7.13.3.10	RegisterEvent(uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0	86
7.13.3.11	UnRegisterEvent2(uint32_t eventType, lpxCam::EventCallback2 *eventCallback, void *pPrivate)=0	87
7.13.3.12	UnRegisterEvent(uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0	87
7.13.3.13	GetParameters(lpxCamErr *err=nullptr)=0	87
7.13.3.14	CreateDeviceFromConfig(const char *fileName, lpxCamErr *err=nullptr)=0	87
7.14	lpxCam::List<_T> Class Template Reference	88
7.14.1	Detailed Description	88
7.14.2	Member Typedef Documentation	90
7.14.2.1	elem_type	90
7.14.3	Constructor & Destructor Documentation	90
7.14.3.1	~List()	90
7.14.4	Member Function Documentation	90
7.14.4.1	Release()=0	90
7.14.4.2	GetCount()=0	90
7.14.4.3	GetFirst()=0	91
7.14.4.4	GetNext()=0	91
7.15	lpxGenParam::Param Class Reference	91
7.15.1	Detailed Description	93
7.15.2	Constructor & Destructor Documentation	93
7.15.2.1	~Param()	93
7.15.3	Member Function Documentation	94
7.15.3.1	GetType()=0	94
7.15.3.2	GetName()=0	94
7.15.3.3	GetToolTip()=0	94

7.15.3.4	GetDescription()=0	94
7.15.3.5	GetDisplayName()=0	94
7.15.3.6	GetVisibility()=0	95
7.15.3.7	IsValueCached()=0	95
7.15.3.8	IsAvailable()=0	95
7.15.3.9	IsWritable()=0	95
7.15.3.10	IsReadable()=0	95
7.15.3.11	IsStreamable()=0	95
7.15.3.12	IsVisible(Visibility vis)=0	95
7.15.3.13	RegisterEventSink(ParamEventSink *aEventSink)=0	96
7.15.3.14	UnregisterEventSink(ParamEventSink *aEventSink)=0	96
7.15.3.15	GetNode()=0	96
7.15.3.16	ToCategory()=0	97
7.15.3.17	ToBoolean()=0	97
7.15.3.18	ToCommand()=0	97
7.15.3.19	ToEnumEntry()=0	97
7.15.3.20	ToEnum()=0	97
7.15.3.21	ToFloat()=0	98
7.15.3.22	ToInt()=0	98
7.15.3.23	ToString()=0	98
7.16	IpxGenParam::ParamEventSink Class Reference	98
7.16.1	Detailed Description	98
7.16.2	Member Function Documentation	98
7.16.2.1	OnParameterUpdate(Param *param)=0	98
7.17	IpxCam::Stream Class Reference	99
7.17.1	Detailed Description	100
7.17.2	Constructor & Destructor Documentation	100
7.17.2.1	~Stream()	100

7.17.3 Member Function Documentation	101
7.17.3.1 Release()=0	101
7.17.3.2 CreateBuffer(size_t iSize, void *pPrivate, lpxCamErr *err)=0	101
7.17.3.3 SetBuffer(void *pBuffer, size_t iSize, void *pPrivate, lpxCamErr *err)=0	101
7.17.3.4 RevokeBuffer(lpxCam::Buffer *buff)=0	102
7.17.3.5 QueueBuffer(lpxCam::Buffer *buff)=0	102
7.17.3.6 GetBuffer(uint64_t iTimeout, lpxCamErr *err=nullptr)=0	102
7.17.3.7 CancelBuffer()=0	103
7.17.3.8 FlushBuffers(FlushOperation operation)=0	103
7.17.3.9 StartAcquisition(uint64_t iNumFramesToAcquire=UINT64_MAX, uint32_t flags=0)=0	103
7.17.3.10 StopAcquisition(uint32_t flags=0)=0	104
7.17.3.11 AllocBufferQueue(void *pPrivate, size_t iNum)=0	104
7.17.3.12 ReleaseBufferQueue()=0	104
7.17.3.13 GetBufferQueueSize()=0	105
7.17.3.14 RegisterEvent(uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0	105
7.17.3.15 UnRegisterEvent(uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0	105
7.17.3.16 GetParameters(lpxCamErr *err=nullptr)=0	106
7.17.3.17 GetNumDelivered()=0	106
7.17.3.18 GetNumUnderrun()=0	106
7.17.3.19 GetNumAnnounced()=0	107
7.17.3.20 GetNumQueued()=0	107
7.17.3.21 GetNumAwaitDelivery()=0	107
7.17.3.22 GetBufferSize()=0	107
7.17.3.23 IsGrabbing()=0	108
7.17.3.24 GetMinNumBuffers()=0	108
7.17.3.25 GetBufferAlignment()=0	108
7.18 lpxGenParam::String Class Reference	108

7.18.1 Detailed Description	109
7.18.2 Member Function Documentation	109
7.18.2.1 GetType()	109
7.18.2.2 GetMaxLength(IpxCamErr *err=nullptr)=0	109
7.18.2.3 GetValue(size_t *len=nullptr, IpxCamErr *err=nullptr)=0	110
7.18.2.4 SetValue(const char *val)=0	110
7.19 IpxCam::System Class Reference	111
7.19.1 Detailed Description	111
7.19.2 Constructor & Destructor Documentation	112
7.19.2.1 ~System()	112
7.19.3 Member Function Documentation	112
7.19.3.1 Release()=0	112
7.19.3.2 GetInterfaceList(InterfaceType type=AllInterfaces)=0	113
7.19.3.3 GetInterfaceById(const char *ifaceId)=0	114
7.19.3.4 GetDisplayName()=0	115
7.19.3.5 GetVersion()=0	116
7.19.3.6 CreateDeviceFromConfig(const char *fileName, IpxCamErr *err=nullptr)=0	116
7.19.3.7 RegisterGenTLProvider(const char *fileName)=0	116

Chapter 1

Imperx Camera C++ SDK

1.1 General Information

The Imperx Camera C++ SDK is designed to provide software developers with C++ API functionality for ease of integrating Imperx cameras into their software applications. The API implemented in two libraries: `lpxCameraApi` and `lpxCameraGuiApi`. `lpxCameraApi` includes two namespaces: `lpxCam` and `lpxGenParam`. `lpxCameraGuiApi` includes `lpxGui` namespace.

The `lpxCam` namespace provides the scope to the API of GenICam GenTL transport layer to acquire images with an Imperx Camera. The `lpxGenParam` namespace provides the scope to the API to control the GenICam camera parameters, like image Width, Height, Pixel Format, Gain, Exposure, Trigger settings, etc. `lpxGui` namespace provides the scope for the user interface features, like windows and panels.

1.2 lpxCameraApi library

`lpxCameraApi` library includes classes, functions and types of `lpxCam` and `lpxGenParam` namespaces. It uses Imperx GenTL Producer library `lpxCTI.cti` to communicate with the cameras

1.2.1 lpxCam namespace

The `lpxCam` namespace consist of several main classes that represent the GenTL modules. The main classes are

- `lpxCam::System` - The System class is the entry point to the GenTL Producer software driver.
- `lpxCam::Interface` - The Interface class provides method to represents an individual physical interface, like GigE or USB3
- `lpxCam::Device` - The Device class provides methods to enable the communication with the camera device and enumerate/instantiate the video data streams.

- [IpxCam::Stream](#) - The Stream class purpose is to access the image buffer data acquirement from the Acquisition engine.
- [IpxCam::Buffer](#) - The Buffer class contains the methods to access the image data and parameters of the acquired image buffer.

Example of GenTL System Hierarchy

1.2.2 IpxGenParam namespace

The [IpxGenParam](#) namespace consist of the following main classes to access the GenICam parameters features. The main classes are

- [IpxGenParam::Param](#) - General class for accessing the GenICam feature node of the Camera parameters.
- [IpxGenParam::Boolean](#) - Class representing the Boolean GenICam camera parameter.
- [IpxGenParam::Command](#) - Class representing the Command GenICam camera parameter.
- [IpxGenParam::Enum](#) - Class representing the Enumeration GenICam camera parameter.
- [IpxGenParam::Float](#) - Class representing the Float GenICam camera parameter.
- [IpxGenParam::Int](#) - Class representing the Integer GenICam camera parameter.
- [IpxGenParam::String](#) - Class representing the String GenICam camera parameter.

1.3 IpxCameraGuiApi library

IpxCameraGuiApi library includes classes, functions and types of [IpxGui](#) namespace. The [IpxGui](#) namespace consist of the following GUI API classes and functions:

- [IpxGui::SelectCameraA](#) - function to show the modal dialog window of camera selection
- [IpxGui::SelectCameraW](#) - unicode version of [IpxGui::SelectCameraA](#)
- [IpxGui::CreateGenParamTreeViewForArrayA](#) - function to show the modeless dialog window of the camera GenICam parameters
- [IpxGui::CreateGenParamTreeViewForArrayW](#) - unicode version of [IpxGui::CreateGenParamTreeViewForArrayA](#)
- [IpxGui::DestroyGenParamTreeView](#) - function to destroy the modeless dialog window of the camera GenICam parameters, created with [IpxGui::CreateGenParamTreeViewForArrayA](#) function call
- [IpxGui::IpxGenParamTreeView](#) - Interface class for the modeless dialog window of the camera GenICam parameters. This class provides methods to set visibility level and parameters tree state.
- [IpxGui::IpxGenParamTreeView](#) - QT class, based on QWidget for the modeless window of the camera GenICam parameters.
- [IpxGui::IpxCameraSelectorDialog](#) - QT class, based on QDialog for the modal dialog window of camera selection

Chapter 2

Deprecated List

Member `lpxCam::Device::RegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *pPrivate`)=0

Use `Device::RegisterEvent2` instead

Member `lpxCam::Device::UnRegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *pPrivate`)=0

Use `Device::UnRegisterEvent2` instead

Member `lpxCam::EventCallback` (`const void *eventData`, `size_t eventSize`, `void *pPrivate`)

Use `EventCallback2` instead

Member `lpxCam::Interface::RegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *pPrivate`)=0

Use `RegisterEvent2` instead

Member `lpxCam::Interface::UnRegisterEvent` (`uint32_t eventType`, `lpxCam::EventCallback *eventCallback`, `void *pPrivate`)=0

Use `UnRegisterEvent2` instead

Chapter 3

Namespace Index

3.1 Namespace List

Here is a list of all documented namespaces with brief descriptions:

lpxCam	A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera	11
lpxGenParam	A namespace provides the scope to the API to access the GenICam parameters	14
lpxGui	The lpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions	16

Chapter 4

Hierarchical Index

4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

IpxGenParam::Array	27
IpxCam::Buffer	42
IpxCam::Device	51
IpxCam::DeviceInfo	57
IpxGui::IpxGenParamTreeView	73
IpxCam::Interface	82
IpxCam::List< _T >	88
IpxGenParam::Param	91
IpxGenParam::Boolean	40
IpxGenParam::Category	47
IpxGenParam::Command	49
IpxGenParam::Enum	63
IpxGenParam::EnumEntry	67
IpxGenParam::Float	69
IpxGenParam::Int	79
IpxGenParam::String	108
IpxGenParam::ParamEventSink	98
IpxCam::Stream	99
IpxCam::System	111

Chapter 5

Class Index

5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

lpxGenParam::Array	
An Array class contains methods to access all GenICam camera parameters	27
lpxGenParam::Boolean	
A class containing methods for Boolean GenICam camera parameter	40
lpxCam::Buffer	
Buffer module in the GenTL module hierarchy	42
lpxGenParam::Category	
A class containing methods for GenICam Category	47
lpxGenParam::Command	
A class containing methods for Command GenICam camera parameter	49
lpxCam::Device	
Device module in the GenTL module hierarchy	51
lpxCam::DeviceInfo	
DeviceInfo class provides the information about the camera device	57
lpxGenParam::Enum	
A class containing methods for Enumeration GenICam camera parameter	63
lpxGenParam::EnumEntry	
EnumEntry class represents the entry of GenICam Enum parameter	67
lpxGenParam::Float	
A class containing methods for Float GenICam camera parameter	69
lpxGui::IlpxGenParamTreeView	
IlpxGenParamTreeView class represents the GenICam parameters node tree panel	73
lpxGenParam::Int	
A class containing methods for Integer GenICam camera parameter	79
lpxCam::Interface	
Interface module in the GenTL module hierarchy	82
lpxCam::List<_T>	
The List class is used as list-like container for the specified template type objects	88
lpxGenParam::Param	
General class for GenICam parameter	91
lpxGenParam::ParamEventSink	
A Class for ParamEventSink notifications handling	98

lpxCam::Stream	
Data stream module in the GenTL module hierarchy	99
lpxGenParam::String	
A class containing methods for String GenlCam camera parameter	108
lpxCam::System	
Abstraction of the System module of the GenTL module hierarchy	111

Chapter 6

Namespace Documentation

6.1 IpxCam Namespace Reference

A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera.

Classes

- class [Buffer](#)
The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.
- class [Device](#)
The [Device](#) class represents the device module in the GenTL module hierarchy.
- class [DeviceInfo](#)
[DeviceInfo](#) class provides the information about the camera device.
- class [Interface](#)
The [Interface](#) class represents a interface module in the GenTL module hierarchy.
- class [List](#)
The [List](#) class is used as list-like container for the specified template type objects.
- class [Stream](#)
The [Stream](#) class represents the data stream module in the GenTL module hierarchy.
- class [System](#)
The [System](#) class represents an abstraction of the [System](#) module of the GenTL module hierarchy.

Typedefs

- typedef [List](#)< [Interface](#) > [InterfaceList](#)
- typedef [List](#)< [DeviceInfo](#) > [DeviceInfoList](#)
- typedef [List](#)< [Device](#) > [DeviceList](#)
- typedef void IPXCAM_CALL [EventCallback](#)(const void *eventData, size_t eventSize, void *pPrivate)
- typedef void IPXCAM_CALL [EventCallback2](#)(uint32_t eventType, const void *eventData, size_t eventSize, void *pPrivate)
[EventCallback2](#).

Enumerations

Functions

- IPXCAM_EXTERN_C IPX_CAMERA_API [System](#) * [IpxCam_GetSystem](#) ()

Returns the [System](#) object pointer.

6.1.1 Detailed Description

A namespace providing scope to the GenICam GenTL transport layer interface to acquire images with an Imperx Camera.

[IpxCam](#) namespace includes classes that represent the base GenTLtransport layer modules: [System](#), [Interface](#), [Device](#), [Stream](#), [Buffer](#). These modules can be used to enumerate the interfaces in the system, enumerate the cameras, connected to each interface, connect to necessary camera, allocate the memory buffers for images, and run the video acquisition.

6.1.2 Typedef Documentation

6.1.2.1 typedef List<Interface> IpxCam::InterfaceList

List of [Interface](#) objects

6.1.2.2 typedef List<DeviceInfo> IpxCam::DeviceInfoList

List of [DeviceInfo](#) objects

6.1.2.3 typedef List<Device> IpxCam::DeviceList

List of [Device](#) objects

6.1.2.4 typedef void IPXCAM_CALL IpxCam::EventCallback(const void *eventData, size_t eventSize, void *pPrivate)

EventCallback

Deprecated Use EventCallback2 instead

6.1.2.5 `typedef void IPXCAM_CALL IpxCam::EventCallback2(uint32_t eventType, const void *eventData, size_t eventSize, void *pPrivate)`

EventCallback2.

Callback function type for Event handling param[in] eventType type of the arrived event param[in] eventData pointer to event Data param[in] eventSize event Size param[in] pPrivate pointer to the context Data

6.1.3 Enumeration Type Documentation

6.1.3.1 `enum IpxCam::InterfaceType : uint32_t`

An enum of [Interface](#) Types. [Interface](#) Node Types representing physical interface in the system.

Enumerator

USB3Vision Enum value for USB3Vision camera interface.

GigEVision Enum value for GigEVision camera interface

CameraLink Enum value for CameraLink camera interface

CoaxPress Enum value for CoaxPress camera interface

HdSdi Enum value for HD-SDI camera interface

AllInterfaces Enum value AllInterfaces.

6.1.3.2 `enum IpxCam::FlushOperation : uint32_t`

An enum of Flush Operations. Flush Operations Types.

Enumerator

Flush_OutputDiscard Enum value Flush_OutputDiscard. Discards all buffers in the output queue and if necessary remove the entries from the event data queue.

Flush_AllToInput Enum value Flush_AllToInput. Puts all buffers in the input pool. Even those in the output queue and discard entries in the event data queue.

Flush_UnqueuedToInput Enum value Flush_UnqueuedToInput. Puts all buffers that are not in the input pool or the output queue in the input pool.

Flush_AllDiscard Enum value Flush_AllDiscard. Discards all buffers in the input pool and output queue.

6.1.3.3 `enum IpxCam::DeviceAccess : uint32_t`

An enum of [Device](#) Access.

Enumerator

ReadOnly Enum value ReadOnly.

Control Enum value Control.

Exclusive Enum value Exclusive.

6.1.4 Function Documentation

6.1.4.1 IPXCAM_EXTERN_C IPX_CAMERA_API System* lpxCam::lpxCam_GetSystem ()

Returns the [System](#) object pointer.

This method returns the [System](#) module object. [System](#) object is being created as soon as API library is loaded. It is the entry point to the GenTL Module hierarchy.

Returns

Returns the pointer to system.

Here is the caller graph for this function:



6.2 lpxGenParam Namespace Reference

A namespace provides the scope to the API to access the GenICam parameters.

Classes

- class [Array](#)
An [Array](#) class contains methods to access all GenICam camera parameters.
- class [Boolean](#)
A class containing methods for [Boolean](#) GenICam camera parameter.
- class [Category](#)
A class containing methods for GenICam [Category](#).
- class [Command](#)
A class containing methods for [Command](#) GenICam camera parameter.
- class [Enum](#)
A class containing methods for Enumeration GenICam camera parameter.
- class [EnumEntry](#)
[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.
- class [Float](#)
A class containing methods for [Float](#) GenICam camera parameter.
- class [Int](#)
A class containing methods for Integer GenICam camera parameter.
- class [Param](#)
General class for GenICam parameter.
- class [ParamEventSink](#)
A Class for [ParamEventSink](#) notifications handling.
- class [String](#)
A class containing methods for [String](#) GenICam camera parameter.

Enumerations

6.2.1 Detailed Description

A namespace provides the scope to the API to access the GenICam parameters.

The [IpxGenParam](#) namespace provides the scope to the API to control the GenICam camera parameters of types: [Boolean](#), Enumeration, [String](#), [Float](#), Integer, Commands and Categories. Such parameters may include image Width, Height, Pixel Format, Gain, Exposure, Trigger, I/O settings, etc. Parameters are described in camera GenICam XML file, and documented in appropriate camera user's manual.

6.2.2 Enumeration Type Documentation

6.2.2.1 enum IpxGenParam::ParamType : uint32_t

An enumeration of Parameter Types. Parameter Node Types that can access the node object's programming interface.

Enumerator

ParamUnknown [Enum](#) value ParamUnknown. Unknown Parameter.

ParamInt [Enum](#) value ParamInt will access node object's of IInteger interface.

ParamFloat [Enum](#) value ParamFloat will access node object's of IFloat interface.

ParamString [Enum](#) value ParamString will access node object's of IString interface.

ParamEnum [Enum](#) value ParamEnum will access node object's of IEnumeration interface.

ParamEnumEntry [Enum](#) value ParamEnumEntry will access the entry of [Enum](#) parameter.

ParamBoolean [Enum](#) value ParamBoolean will access node object's of IBoolean interface.

ParamCommand [Enum](#) value ParamCommand will access node object's of ICommand interface.

ParamCategory [Enum](#) value ParamCategory will access node object's of ICategory interface.

6.2.2.2 enum IpxGenParam::NameSpace : uint32_t

An enumeration of GenICam NameSpace. Parameter Node Namespace.

Enumerator

NameSpaceStandard [Enum](#) value NameSpaceStandard. Identifies the standard namespace used in the file.

NameSpaceCustom [Enum](#) value NameSpaceCustom. Identifies the custom namespace used in the file.

NameSpaceUndefined [Enum](#) value NameSpaceUndefined. Unknown namespace.

6.2.2.3 enum `lpxGenParam::Visibility` : `uint32_t`

An enumeration of Visibility. This element defines the level of user that has access to the feature.

Enumerator

VisBeginner Enum value VisBeginner. User has visibility to all the basic features of the device.

VisExpert Enum value VisExpert. User has visibility to more advance features of the device.

VisGuru Enum value VisGuru. User has visibility to even more advance features that if set improperly can cause device to be in an improper state.

VisInvisible Enum value VisInvisible. Not visible.

VisUndefined Enum value VisUndefined. Unknown visibility.

6.3 lpxGui Namespace Reference

The lpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions.

Classes

- class `lpxGenParamTreeView`
lpxGenParamTreeView class represents the GenICam parameters node tree panel.

Enumerations

Functions

- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API lpxGenParamTreeView * CreateGenParamTreeViewForArrayA (lpxGenParam::Array *genParam, const char *title, uintptr_t parentWindow=0)`
Creates the panel of the camera GenICam parameters for lpxGenParam::Array object.
- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API lpxGenParamTreeView * CreateGenParamTreeViewForArrayW (lpxGenParam::Array *genParam, const wchar_t *title, uintptr_t parentWindow=0)`
Creates the panel of the camera GenICam parameters for lpxGenParam::Array object. Unicode version.
- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API lpxGenParamTreeView * CreateGenParamTreeViewForNodemapA (IPX_GENAPI_NS::INodeMap *nodemap, const char *title, uintptr_t parentWindow=0)`
Creates the panel of the camera GenICam parameters for GenApi::INodeMap object.
- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API lpxGenParamTreeView * CreateGenParamTreeViewForNodemapW (IPX_GENAPI_NS::INodeMap *nodemap, const wchar_t *title, uintptr_t parentWindow=0)`
Creates the panel of the camera GenICam parameters for GenApi::INodeMap object. Unicode version.
- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void DestroyGenParamTreeView (lpxGenParamTreeView *view)`
Destroys the GenICam parameters panel.
- `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API lpxCam::DeviceInfo * SelectCameraA (lpxCam::System *pSystem, const char *title, uintptr_t parentWindow=0, bool poll=true)`

Pops-up the camera selection dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API [IpxCam::DeviceInfo](#) * [SelectCameraW](#) ([IpxCam::System](#) *pSystem, const wchar_t *title, uintptr_t parentWindow=0, bool poll=true)

Pops-up the camera selection dialog. Unicode version.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowCamConfigDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Camera Configuration Dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowFrameABDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)
- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowTriggerDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Trigger Dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowPulseDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Pulse Dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowStrobeDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Strobe Dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowOutputDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Output Data Dialog.

- IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [ShowColorDialog](#) ([IpxCam::Device](#) *device, uintptr_t parentWindow=0)

Show Color Dialog.

6.3.1 Detailed Description

The IpxGUI namespace is a declarative region that provides a scope to the Imperx Camera GUI API classes and functions.

The IpxGUI namespace includes Imperx Camera GUI API classes and functions, such as: [IpxGenParamTreeView](#), [SelectCameraA](#) [SelectCameraW](#) [IpxGenParamTreeView](#), [IpxCameraSelectorDialog](#)

6.3.2 Enumeration Type Documentation

6.3.2.1 enum [IpxGui::Visibility](#) : uint32_t

An enum of Visibility. Defines the visibility type of features that user will see in the Tree View.

Enumerator

Beginner Enum value Beginner. User has visibility to all the basic features of the device.

Expert Enum value Expert. User has visibility to more advance features of the device.

Guru Enum value Guru. User has visibility to even more advance features that if set improperly can cause device to be in an improper state.

6.3.3 Function Documentation

6.3.3.1 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IlpxGenParamTreeView* IpxGui::CreateGenParamTreeViewForArrayA (IpxGenParam::Array * *genParam*, const char * *title*, uintptr_t *parentWindow* = 0)

Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object.

This function returns the pointer to the [IlpxGenParamTreeView](#) class that was created using information extracted from the [IpxGenParam::Array](#) class.

Parameters

in	<i>genParam</i>	The pointer to the IpxGenParam::Array class.
in	<i>title</i>	The title of the IlpxGenParamTreeView class as a const char.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Returns

If the function succeeds, the return value is the pointer to the [IlpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



6.3.3.2 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IlpxGenParamTreeView* IpxGui::CreateGenParamTreeViewForArrayW (IpxGenParam::Array * *genParam*, const wchar_t * *title*, uintptr_t *parentWindow* = 0)

Creates the panel of the camera GenICam parameters for [IpxGenParam::Array](#) object. Unicode version.

This function returns the pointer to the [IlpxGenParamTreeView](#) class that was created using information extracted from the [IpxGenParam::Array](#).

Parameters

in	<i>genParam</i>	The pointer to the IpxGenParam::Array class.
in	<i>title</i>	The title of the IlpxGenParamTreeView class as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Returns

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



6.3.3.3 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxGenParamTreeView* IpxGui::CreateGenParamTreeViewForNodemapA (IPX_GENAPI_NS::INodeMap * *nodemap*, const char * *title*, uintptr_t *parentWindow* = 0)

Creates the panel of the camera GenICam parameters for GenApi::INodeMap object.

This function returns the pointer to the [IpxGenParamTreeView](#) class that was created using information extracted from the GenApi::INodeMap class.

Parameters

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
in	<i>title</i>	The title of the IpxGenParamTreeView class as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Returns

If the function succeeds, the return value is the pointer to the [IpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



6.3.3.4 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API [IlpxGenParamTreeView](#)* [IpxGui::CreateGenParamTreeViewForNodemapW](#) ([IPX_GENAPI_NS::INodeMap](#) * *nodemap*, const wchar_t * *title*, uintptr_t *parentWindow* = 0)

Creates the panel of the camera GenICam parameters for [GenApi::INodeMap](#) object. Unicode version.

This function returns the pointer to the [IlpxGenParamTreeView](#) that was created using information extracted from the [GenApi::INodeMap](#) class.

Parameters

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
in	<i>title</i>	The title of the IlpxGenParamTreeView as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Returns

If the function succeeds, the return value is the pointer to the [IlpxGenParamTreeView](#) class created. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



6.3.3.5 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void [IpxGui::DestroyGenParamTreeView](#) ([IlpxGenParamTreeView](#) * *view*)

Destroys the GenICam parameters panel.

This function closes the camera GenICam parameters panel and destroys the [IlpxGenParamTreeView](#) object previously created with [CreateGenParamTreeViewForNodemap*](#) or [CreateGenParamTreeViewForArray*](#) function


Parameters

in	<i>view</i>	A pointer to the IlpxGenParamTreeView class.
----	-------------	--

Returns

void

Here is the caller graph for this function:



6.3.3.6 `IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API IpxCam::DeviceInfo* IpxGui::SelectCameraA (IpxCam::System * pSystem, const char * title, uintptr_t parentWindow = 0, bool poll = true)`

Pops-up the camera selection dialog.

This function pops-up the "Select camera" modal dialog, where user can select the Camera and obtain the pointer to [IpxCam::DeviceInfo](#) object for the selected camera


Parameters

in	<i>pSystem</i>	The pointer to the IpxCam::System class.
in	<i>title</i>	The title of the selected Camera as a const char variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget
in	<i>poll</i>	Specifies if poll check box should be checked by default, so the System will be polled for new devices to appear

Returns

If the function succeeds, the return value is the pointer to the [IpxCam::DeviceInfo](#) class. Otherwise, the return value is nullptr.

Here is the caller graph for this function:



6.3.3.7 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API **IpxCam::DeviceInfo*** IpxGui::SelectCameraW (**IpxCam::System** * *pSystem*, const wchar_t * *title*, uintptr_t *parentWindow* = 0, bool *poll* = true)

Pops-up the camera selection dialog. Unicode version.

This function pops-up the "Select camera" modal dialog, where user can select the Camera and obtain the pointer to [IpxCam::DeviceInfo](#) object for the selected camera.


Parameters

in	<i>pSystem</i>	The pointer to the IpxCam::System class.
in	<i>title</i>	The title of the IpxGenParamTreeView as a wchar_t variable.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget
in	<i>poll</i>	Specifies if poll check box should be checked by default, so the System will be polled for new devices to appear

Returns

If the function succeeds, the return value is the pointer to the [IpxCam::DeviceInfo](#) class. Otherwise, the return value is nullptr.

Here is the caller graph for this function:




6.3.3.8 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowCamConfigDialog (**IpxCam::Device** * *device*, uintptr_t *parentWindow* = 0)

Show Camera Configuration Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



6.3.3.9 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowFrameABDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:




6.3.3.10 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowTriggerDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Show Trigger Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:




6.3.3.11 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowPulseDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Show Pulse Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:




6.3.3.12 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowStrobeDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Show Strobe Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:




6.3.3.13 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowOutputDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Show Output Data Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:




6.3.3.14 IPXCAM_GUI_EXTERN_C IPX_CAMERA_GUI_API void IpxGui::ShowColorDialog (IpxCam::Device * *device*, uintptr_t *parentWindow* = 0)

Show Color Dialog.

Parameters

in	<i>device</i>	The pointer to the IpxCam::Device class.
in	<i>parentWindow</i>	A pointer to the parent Window. If the parent is set to 0, this widget is setup to become a window. If not this widget becomes a child widget

Here is the caller graph for this function:



Chapter 7

Class Documentation

7.1 IpxGenParam::Array Class Reference

An [Array](#) class contains methods to access all GenICam camera parameters.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~Array](#) ()
Array class destructor.
- virtual [Param](#) * [GetParam](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Param](#) class object for the specified node name from the node map declared in the camera descriptor XML file.
- virtual [Boolean](#) * [GetBoolean](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Boolean](#) class object for the specified node name of the camera descriptor XML file.
- virtual [Command](#) * [GetCommand](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Command](#) class object for the specified node name of the camera descriptor XML file.
- virtual [Enum](#) * [GetEnum](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Enum](#) class object for the specified node name of the camera descriptor XML file.
- virtual [Float](#) * [GetFloat](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Float](#) class object for the specified node name of the camera descriptor XML file.
- virtual [Int](#) * [GetInt](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [Int](#) class object for the specified node name of the camera descriptor XML file.
- virtual [String](#) * [GetString](#) (const char *name, IpxCamErr *err)=0
This method gets the pointer to the [String](#) class object for the specified node name of the camera descriptor XML file.
- virtual [Category](#) * [GetRootCategory](#) (IpxCamErr *err)=0
This method gets the pointer to the root category node object. The Root node is considered a special node. It has no parent node. In the topology graph, it is the top node which connects to at least one child node. The child node may connect to the device node that provides the connection to the transport layer.
- virtual IPX_GENAPI_NS::INodeMap * [GetNodeMap](#) (IpxCamErr *err)=0

This method gets the pointer to the NodeMap interface. The NodeMap interface will provide methods to retrieves all nodes in the node map.

- virtual uint32_t [GetCount](#) ()=0

This method gets the number of nodes.

- virtual [Param](#) * [GetParamByIndex](#) (uint32_t idx, [lpxCamErr](#) *err)=0

This method gets the parameter by index.

- virtual [lpxCamErr](#) [SetBooleanValue](#) (const char *name, bool aValue)=0

This method sets the [Boolean](#) value of the [Boolean](#) node.

- virtual bool [GetBooleanValue](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [Boolean](#) value of the [Boolean](#) node.

- virtual [lpxCamErr](#) [SetEnumValueStr](#) (const char *name, const char *val)=0

This method sets the [Enum](#) node maps and the [Enum](#) interface to a name and index value. Each of the enum entries are represented by a name and index pair. This method sets the [Enum](#) value [String](#) of the corresponding node. The enum nodes map to a drop down box.

- virtual [lpxCamErr](#) [SetEnumValue](#) (const char *name, int64_t val)=0

This method sets the [Enum](#) value of the enum node.

- virtual const char * [GetEnumValueStr](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [Enum](#) value string of the current set [Enum](#) value entry.

- virtual int64_t [GetEnumValue](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [Enum](#) value of the [Enum](#) node.

- virtual [lpxCamErr](#) [SetFloatValue](#) (const char *name, double val)=0

This method sets the [Float](#) value of the [Float](#) node.

- virtual double [GetFloatValue](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [Float](#) value of the [Float](#) node.

- virtual [lpxCamErr](#) [SetIntegerValue](#) (const char *name, int64_t val)=0

This method sets the [Integer](#) value of the [Integer](#) node.

- virtual int64_t [GetIntegerValue](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [Integer](#) value of the [Integer](#) node.

- virtual [lpxCamErr](#) [SetStringValue](#) (const char *name, const char *val)=0

This method sets the [String](#) value of the [String](#) node.

- virtual const char * [GetStringValue](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method gets the [String](#) value of the [String](#) node.

- virtual [lpxCamErr](#) [ExecuteCommand](#) (const char *name)=0

This method executes/submits the command.

- virtual bool [IsCommandDone](#) (const char *name, [lpxCamErr](#) *err=nullptr)=0

This method polls the corresponding executed command to see if the executed command is done or not.

- virtual [lpxCamErr](#) [Poll](#) (int64_t elapsedTime)=0

This method fires nodes which have a polling time.

7.1.1 Detailed Description

An [Array](#) class contains methods to access all GenICam camera parameters.

This class contains methods that can access each node from the GenICam camera description XML file by parameters type and name.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 `virtual IpxGenParam::Array::~Array () [inline],[virtual]`

[Array](#) class destructor.

[Array](#) class destructor. Destroys the [Array](#) object and all its descendants.

7.1.3 Member Function Documentation

7.1.3.1 `virtual Param* IpxGenParam::Array::GetParam (const char * name, IpxCamErr * err) [pure virtual]`

This method gets the pointer to the [Param](#) class object for the specified node name from the node map declared in the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of a node in node map.
out	<i>err</i>	Returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Param class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - specified node name not found in camera descriptor XML file

Returns

If the method succeeds, it returns the pointer to the [Param](#) class for the specific node name. Otherwise, it returns a nullptr.

7.1.3.2 `virtual Boolean* IpxGenParam::Array::GetBoolean (const char * name, IpxCamErr * err) [pure virtual]`

This method gets the pointer to the [Boolean](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	A unique name of Boolean type node in the camera descriptor XML file.
out	<i>err</i>	Returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Boolean class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file

Returns

If the method succeeds, it returns the pointer to the [Boolean](#) class for the specific node name. Otherwise, it returns a nullptr.

7.1.3.3 `virtual Command* IpxGenParam::Array::GetCommand (const char * name, IpxCamErr * err)` [pure virtual]

This method gets the pointer to the [Command](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of Command type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Command class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file

Returns

If method succeeds, it returns the pointer to the [Command](#) class for the specific node name. Otherwise, it returns a nullptr.

7.1.3.4 `virtual Enum* IpxGenParam::Array::GetEnum (const char * name, IpxCamErr * err)` [pure virtual]

This method gets the pointer to the [Enum](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of Enumeration type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Enum class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file

Returns

If the method succeeds, it returns the pointer to the [Enum](#) parameter class for the specific node name. Otherwise, it returns a nullptr.

7.1.3.5 virtual Float* IpxGenParam::Array::GetFloat (const char * *name*, IpxCamErr * *err*) [pure virtual]

This method gets the pointer to the [Float](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of Float type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Float class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file

Returns

If the method succeeds, it returns the pointer to the [Float](#) parameter class for the specific node name

7.1.3.6 virtual Int* IpxGenParam::Array::GetInt (const char * *name*, IpxCamErr * *err*) [pure virtual]

This method gets the pointer to the [Int](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
out	<i>err</i>	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Int class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file

Returns

If the method succeeds, it returns the pointer to the [Int](#) class for the specific node name

7.1.3.7 virtual String* IpxGenParam::Array::GetString (const char * *name*, IpxCamErr * *err*) [pure virtual]

This method gets the pointer to the [String](#) class object for the specified node name of the camera descriptor XML file.

Parameters

in	<i>name</i>	Unique name of String type node in the camera descriptor XML file.
----	-------------	--

Parameters

out	err	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to String class of the specified node name • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified node name not found in camera descriptor XML file
-----	-----	---

Returns

If the method succeeds, it returns the pointer to the [String](#) class for the specific node name

7.1.3.8 `virtual Category* IpxGenParam::Array::GetRootCategory (IpxCamErr * err) [pure virtual]`

This method gets the pointer to the root category node object. The Root node is considered a special node. It has no parent node. In the topology graph, it is the top node which connects to at least one child node. The child node may connect to the device node that provides the connection to the transport layer.

Parameters

out	err	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Category class • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - specified Root node name not found in camera descriptor XML file
-----	-----	---

Returns

Returns the pointer to the [Category](#) (root node) class

7.1.3.9 `virtual IPX_GENAPI_NS::INodeMap* IpxGenParam::Array::GetNodeMap (IpxCamErr * err) [pure virtual]`

This method gets the pointer to the NodeMap interface. The NodeMap interface will provide methods to retrieves all nodes in the node map.

Parameters

out	err	returns an error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to <code>GenApi::INodeMap</code> class • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - the node map does not exist
-----	-----	---

Returns

nodemap returns the pointer to the NodeMap interface

7.1.3.10 `virtual uint32_t IpxGenParam::Array::GetCount () [pure virtual]`

This method gets the number of nodes.

Returns

The number of nodes. This number should be greater than 0.

7.1.3.11 `virtual Param* IpxGenParam::Array::GetParamByIndex (uint32_t idx, IpxCamErr * err) [pure virtual]`

This method gets the parameter by index.

Parameters

in	idx	Index
out	err	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to Param class • <code>IpxCamErr::IPX_CAM_ERR_INVALID_INDEX</code> - entered invalid index

Returns

Returns param pointer to Parameter class of the specified node referenced by the index value

7.1.3.12 `virtual IpxCamErr IpxGenParam::Array::SetBooleanValue (const char * name, bool aValue) [pure virtual]`

This method sets the [Boolean](#) value of the [Boolean](#) node.

Parameters

in	name	Unique name of Boolean node to set
in	aValue	Boolean value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully set the [Boolean](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

7.1.3.13 `virtual bool IpxGenParam::Array::GetBooleanValue (const char * name, IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [Boolean](#) value of the [Boolean](#) node.

Parameters

in	<i>name</i>	Unique name of Boolean node to get
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Boolean value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node

Returns

Returns the [Boolean](#) Value

7.1.3.14 `virtual IpxCamErr IpxGenParam::Array::SetEnumValueStr (const char * name, const char * val) [pure virtual]`

This method sets the [Enum](#) node maps and the [Enum](#) interface to a name and index value. Each of the enum entries are represented by a name and index pair. This method sets the [Enum](#) value [String](#) of the corresponding node. The enum nodes map to a drop down box.

Parameters

in	<i>name</i>	Name of Enum entry node to set
in	<i>val</i>	Enum node string value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Enum](#) Value string
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.1.3.15 `virtual IpxCamErr IpxGenParam::Array::SetEnumValue (const char * name, int64_t val) [pure virtual]`

This method sets the [Enum](#) value of the enum node.

Parameters

in	<i>name</i>	Unique name of Enum entry to set
in	<i>val</i>	Enum entry integer value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully gets the [Enum](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.1.3.16 `virtual const char* IpxGenParam::Array::GetEnumValueStr (const char * name, IpxCamErr * err = nullptr)`
[pure virtual]

This method gets the [Enum](#) value string of the current set [Enum](#) value entry.

Parameters

in	<i>name</i>	Unique name of Enum entry
out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Enum string value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type

Returns

Get the [Enum](#) value [String](#) of the current set [Enum](#) Value Entry

7.1.3.17 `virtual int64_t IpxGenParam::Array::GetEnumValue (const char * name, IpxCamErr * err = nullptr)` [pure virtual]

This method gets the [Enum](#) value of the [Enum](#) node.

Parameters

in	<i>name</i>	Unique name of Enum type node in the camera descriptor XML file.
----	-------------	--

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Enum value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	---

Returns

Returns the [Enum](#) Value

7.1.3.18 `virtual IpxCamErr IpxGenParam::Array::SetFloatValue (const char * name, double val) [pure virtual]`

This method sets the [Float](#) value of the [Float](#) node.

Parameters

in	<i>name</i>	Unique name of Float type node in the camera descriptor XML file.
in	<i>val</i>	Float value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Float](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.1.3.19 `virtual double IpxGenParam::Array::GetFloatValue (const char * name, IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [Float](#) value of the [Float](#) node.

Parameters

in	<i>name</i>	Unique name of Float type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Float value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type

Returns

Returns the [Float](#) value

7.1.3.20 `virtual IpxCamErr IpxGenParam::Array::SetIntegerValue (const char * name, int64_t val) [pure virtual]`

This method sets the Integer value of the Integer node.

Parameters

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
in	<i>val</i>	Integer value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the Integer value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.1.3.21 `virtual int64_t IpxGenParam::Array::GetIntegerValue (const char * name, IpxCamErr * err = nullptr) [pure virtual]`

This method gets the Integer value of the Integer node.

Parameters

in	<i>name</i>	Unique name of Integer type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Integer value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type

Returns

Returns the Integer value

7.1.3.22 `virtual IpxCamErr IpxCamParam::Array::SetStringValue (const char * name, const char * val)` [pure virtual]

This method sets the [String](#) value of the [String](#) node.

Parameters

in	<i>name</i>	Unique name of String type node in the camera descriptor XML file.
in	<i>val</i>	String value to set

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [String](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM` - unknown parameter
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.1.3.23 `virtual const char* IpxCamParam::Array::GetStringValue (const char * name, IpxCamErr * err = nullptr)` [pure virtual]

This method gets the [String](#) value of the [String](#) node.

Parameters

in	<i>name</i>	Unique name of String type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the String value • <code>IpxCamErr::IPX_CAM_GENICAM_UNKNOWN_PARAM</code> - unknown parameter • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type

Returns

Returns the [String](#) value

7.1.3.24 `virtual IpxCamErr IpxCamParam::Array::ExecuteCommand (const char * name)` [pure virtual]

This method executes/submits the command.

Parameters

in	<i>name</i>	Unique name of Command type node in the camera descriptor XML file.
----	-------------	---

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully determines state of executed command.
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

7.1.3.25 `virtual bool IpxGenParam::Array::IsCommandDone (const char * name, IpxCamErr * err = nullptr) [pure virtual]`

This method polls the corresponding executed command to see if the executed command is done or not.

Parameters

in	<i>name</i>	Unique name of Command type node in the camera descriptor XML file.
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully determines state of executed command. • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node

Returns

Returns true if the Execute command has finished. Otherwise, returns false.

7.1.3.26 `virtual IpxCamErr IpxGenParam::Array::Poll (int64_t elapsedTime) [pure virtual]`

This method fires nodes which have a polling time.

Parameters

in	<i>elapsedTime</i>	Time elapsed since last poll in msec
----	--------------------	--------------------------------------

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully determines state of executed command.
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.2 IpxGenParam::Boolean Class Reference

A class containing methods for [Boolean](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Boolean:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [Boolean](#) type.
- virtual IpxCamErr [SetValue](#) (bool val)=0
This method can be used to set the node value to true or false.
- virtual bool [GetValue](#) (IpxCamErr *err=nullptr)=0
This method returns the node value. It can return a true or false value.

7.2.1 Detailed Description

A class containing methods for [Boolean](#) GenICam camera parameter.

A class containing methods that map the integer element value of a GenICam IBoolean interface feature to true or false.

For example, the mapping below will illustrate the IBoolean interfaces of a **LUTEnable** feature.

7.2.2 Member Function Documentation

7.2.2.1 virtual ParamType IpxGenParam::Boolean::GetType () [inline],[virtual]

This method returns the node object [Boolean](#) type.

Returns

Returns the node object [Boolean](#) type

Implements [IpxGenParam::Param](#).

7.2.2.2 virtual IpxCamErr IpxGenParam::Boolean::SetValue (bool val) [pure virtual]

This method can be used to set the node value to true or false.

Parameters

in	val	The node value to set such as true or false
----	-----	---

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Boolean](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.2.2.3 virtual bool IpxGenParam::Boolean::GetValue (IpxCamErr * err = nullptr) [pure virtual]

This method returns the node value. It can return a true or false value.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the value of the Boolean node • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	-----	---

Returns

The node value read.

The documentation for this class was generated from the following file:

- IpxCameraApi.h

7.3 IpxCam::Buffer Class Reference

The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~Buffer](#) ()
Buffer class destructor.
- virtual [IpxImage](#) * [GetImage](#) ()=0
Returns the pointer to the IpxImage structure.
- virtual void * [GetBufferPtr](#) ()=0
Returns the pointer to the image data.
- virtual [size_t](#) [GetImageOffset](#) ()=0
Returns the offset of the actual image data start.
- virtual [size_t](#) [GetBufferSize](#) ()=0
This method returns the size of the allocated memory buffer in bytes.
- virtual [uint64_t](#) [GetPixelFormat](#) ()=0
This method returns the pixel format of the buffer object.
- virtual void * [GetUserPtr](#) ()=0
This method returns the user data buffer pointer, associated with the buffer object.
- virtual [uint64_t](#) [GetTimestamp](#) ()=0
This method returns the timestamp of the acquired buffer.
- virtual [uint64_t](#) [GetFrameID](#) ()=0
This method returns the identifier of the image stream block of the buffer object.
- virtual bool [IsIncomplete](#) ()=0
This method returns a flag indicating if the buffer data has been fully transferred or incomplete.
- virtual [size_t](#) [GetWidth](#) ()=0
Returns the image width.
- virtual [size_t](#) [GetHeight](#) ()=0
Returns the image height.
- virtual [size_t](#) [GetXOffset](#) ()=0
Returns the horizontal offset of the image data in the buffer.
- virtual [size_t](#) [GetYOffset](#) ()=0
Returns the vertical offset of the image data in the buffer.
- virtual [size_t](#) [GetXPadding](#) ()=0

This method returns the number of extra bytes padded in the horizontal direction.

- virtual size_t [GetYPadding](#) ()=0

This method returns the number of extra bytes padded in the vertical direction.

- virtual size_t [GetDeliveredHeight](#) ()=0

This method returns the actual height of delivered data.

- virtual bool [IsKacFrameB](#) ()=0

This method indicates if this buffer is Frame A or Frame B, acquired from Cheetah camera with KAC-12040 or KAC-06040 CMOS sensor.

7.3.1 Detailed Description

The [Buffer](#) class represents the buffer module in the GenTL module hierarchy.

The [Buffer](#) class contains the methods that can be used to get the pointer to the acquired image data memory and / or retrieve the information about the received image data such as timestamp, image size, pixel format, etc

7.3.2 Constructor & Destructor Documentation

7.3.2.1 virtual IpxCam::Buffer::~Buffer () [inline],[virtual]

[Buffer](#) class destructor.

Destroys the [Buffer](#) object and all its descendants.

Returns

none

7.3.3 Member Function Documentation

7.3.3.1 virtual IpxImage* IpxCam::Buffer::GetImage () [pure virtual]

Returns the pointer to the IpxImage structure.

This method returns the pointer to the IpxImage structure. See IpxTools user's manual for IpxImage structure description.

Returns

Returns the pointer to the IpxImage structure.

7.3.3.2 `virtual void* lpxCam::Buffer::GetBufferPtr () [pure virtual]`

Returns the pointer to the image data.

This method returns the pointer to the memory of the acquired image data.

Returns

Returns the pointer to the image data

7.3.3.3 `virtual size_t lpxCam::Buffer::GetImageOffset () [pure virtual]`

Returns the offset of the actual image data start.

This method returns the offset of the actual image data start in the acquired data buffer memory.

Returns

Returns the offset of the actual image data start

7.3.3.4 `virtual size_t lpxCam::Buffer::GetBufferSize () [pure virtual]`

This method returns the size of the allocated memory buffer in bytes.

Returns

Returns the buffer size in bytes

7.3.3.5 `virtual uint64_t lpxCam::Buffer::GetPixelFormat () [pure virtual]`

This method returns the pixel format of the buffer object.

Returns

Returns the pixel format of the image in the buffer object. This value equals to **PixeFormat** GenICam parameter

7.3.3.6 `virtual void* lpxCam::Buffer::GetUserPtr () [pure virtual]`

This method returns the user data buffer pointer, associated with the buffer object.

Returns

Returns the user data buffer pointer

7.3.3.7 virtual uint64_t IpxCam::Buffer::GetTimestamp () [pure virtual]

This method returns the timestamp of the acquired buffer.

This method returns the timestamp of the acquired buffer. Imperx USB3 and GEV cameras have 10ns timestamp granularity. GEV cameras timestamp clock frequency can be obtained from **GevTimestampTickFrequency** GenICam parameter

Returns

Returns the timestamp of the acquired buffer.

7.3.3.8 virtual uint64_t IpxCam::Buffer::GetFrameID () [pure virtual]

This method returns the identifier of the image stream block of the buffer object.

Returns

Returns the identifier of the image stream block of the buffer object.

7.3.3.9 virtual bool IpxCam::Buffer::IsIncomplete () [pure virtual]

This method returns a flag indicating if the buffer data has been fully transferred or incompletd.

Returns

Returns True, if buffer transfer was incompletd, False, if transfer was successful

7.3.3.10 virtual size_t IpxCam::Buffer::GetWidth () [pure virtual]

Returns the image width.

This method returns the image width of the buffer data in number of pixels. Usually the return value equals to **Width** GenICam parameter value

Returns

Returns the image width

7.3.3.11 `virtual size_t lpxCam::Buffer::GetHeight () [pure virtual]`

Returns the image height.

This method returns the image height of the buffer data in number of lines. Usually the return value equals to **Height** GenICam parameter value

Returns

Returns the image height

7.3.3.12 `virtual size_t lpxCam::Buffer::GetXOffset () [pure virtual]`

Returns the horizontal offset of the image data in the buffer.

This method returns the horizontal offset of the image data in the buffer in number of pixels from the image origin. Usually the return value equals to **OffsetX** GenICam parameter value

Returns

Returns the horizontal offset in number of pixels

7.3.3.13 `virtual size_t lpxCam::Buffer::GetYOffset () [pure virtual]`

Returns the vertical offset of the image data in the buffer.

This method returns the vertical offset of the image data in the buffer in number of lines from the image origin. Usually the return value equals to **OffsetY** GenICam parameter value

Returns

Returns the vertical offset of the data in the buffer in number of lines from the image origin

7.3.3.14 `virtual size_t lpxCam::Buffer::GetXPadding () [pure virtual]`

This method returns the number of extra bytes padded in the horizontal direction.

Returns

Returns the XPadding of the data in the buffer in number of bytes

7.3.3.15 `virtual size_t IpxCam::Buffer::GetYPadding () [pure virtual]`

This method returns the number of extra bytes padded in the vertical direction.

Returns

Returns the YPadding of the data in the buffer in number of bytes

7.3.3.16 `virtual size_t IpxCam::Buffer::GetDeliveredHeight () [pure virtual]`

This method returns the actual height of delivered data.

This method returns the actual height of delivered data. Can be different than value returned by [GetHeight\(\)](#) method, if image transfer was incompleated.

Returns

Returns the actual height of delivered data

7.3.3.17 `virtual bool IpxCam::Buffer::IsKacFrameB () [pure virtual]`

This method indicates if this buffer is Frame A or Frame B, acquired from Cheetah camera with KAC-12040 or KAC-06040 CMOS sensor.

Returns

Returns true for Frame B, false - otherwise

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.4 IpxGenParam::Category Class Reference

A class containing methods for GenICam [Category](#).

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Category:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [Category](#) type.
- virtual uint32_t [GetCount](#) ()=0
This method returns the number of parameters in the category.
- virtual [Param](#) * [GetParamByIndex](#) (uint32_t idx, [lpxCamErr](#) *err)=0
This method returns the Parameter by Index.

7.4.1 Detailed Description

A class containing methods for GenICam [Category](#).

A class containing methods that the user can access the categories of GenICam features. It will access the node object's of an ICategory interface. Each feature of a device will be placed in a [Category](#). The [Category](#) feature is used to present the user with a group of features for the named category.

For example, the mapping below will illustrate the ICategory interfaces categories such as DeviceControl and Event↵Control.

7.4.2 Member Function Documentation

7.4.2.1 virtual [ParamType](#) [lpxGenParam::Category::GetType](#) () [inline],[virtual]

This method returns the node object [Category](#) type.

Returns

Returns the node object [Category](#) type

Implements [lpxGenParam::Param](#).

7.4.2.2 virtual uint32_t [lpxGenParam::Category::GetCount](#) () [pure virtual]

This method returns the number of parameters in the category.

Returns

Returns the number of parameters in the category

7.4.2.3 virtual [Param](#)* [lpxGenParam::Category::GetParamByIndex](#) (uint32_t idx, [lpxCamErr](#) * err) [pure virtual]

This method returns the Parameter by Index.

Parameters

in	idx	index
out	err	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully returns pointer to the parameter for specified index • <code>IpxCamErr::IPX_CAM_ERR_INVALID_INDEX</code> - an invalid index for node

Returns

Returns the pointer to the parameter object

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

7.5 IpxGenParam::Command Class Reference

A class containing methods for [Command](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for `IpxGenParam::Command`:



Public Member Functions

- virtual [ParamType](#) `GetType` ()
This method returns the node object [Command](#) type.
- virtual `IpxCamErr` [Execute](#) ()=0
This method executes the command.
- virtual bool [IsDone](#) (`IpxCamErr *err=nullptr`)=0
This method queries whether the command is executed and completed.

7.5.1 Detailed Description

A class containing methods for [Command](#) GenICam camera parameter.

A class for GenICam [Command](#) contains methods that allow the user submit a command for execution as well as poll the command status.

For example, the mapping below will illustrate the ICommand interface for AcquisitionStart. This feature starts the Acquisition of the device.

7.5.2 Member Function Documentation

7.5.2.1 virtual ParamType IpxGenParam::Command::GetType () [inline],[virtual]

This method returns the node object [Command](#) type.

Returns

Returns the node object [Command](#) type

Implements [IpxGenParam::Param](#).

7.5.2.2 virtual IpxCamErr IpxGenParam::Command::Execute () [pure virtual]

This method executes the command.

Returns

the error code

7.5.2.3 virtual bool IpxGenParam::Command::IsDone (IpxCamErr * err = nullptr) [pure virtual]

This method queries whether the command is executed and completed.

Parameters

out	err	returns error code:
		<ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully determined that state of execute command • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TREE_ERROR</code> - Unable to access tree

Returns

If set to TRUE, the Execute command has finished. Otherwise, it returns FALSE.

The documentation for this class was generated from the following file:

- IpxCameraApi.h

7.6 IpxCam::Device Class Reference

The [Device](#) class represents the device module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

Public Types**Public Member Functions**

- virtual [~Device](#) ()
A destructor of the [Device](#) class.
- virtual void [Release](#) ()=0
This method releases the instance of the device object. This method releases the device object.
- virtual uint32_t [GetNumStreams](#) ()=0
This method retrieves the number of the data streams, provided by the [Device](#).
- virtual [Stream](#) * [GetStreamByIndex](#) (uint32_t idx=0)=0
This retrieves the pointer to the [Stream](#) object by stream index.
- virtual [Stream](#) * [GetStreamById](#) (const char *id)=0
This method retrieves the pointer to the [Stream](#) object by stream identifier.
- virtual [DeviceInfo](#) * [GetInfo](#) ()=0
This method returns a pointer to the [DeviceInfo](#) object , associated with the [Device](#).
- virtual IpxCamErr [ReadMem](#) (uint64_t addr, void *data, size_t len)=0
This method reads a number of bytes from a given address of the [Device](#).
- virtual IpxCamErr [WriteMem](#) (uint64_t addr, const void *data, size_t len, size_t *written)=0
This method writes a number of bytes at a given address.
- virtual IpxCamErr [RegisterEvent2](#) (uint32_t eventType, [IpxCam::EventCallback2](#) *eventCallback, void *p↔Private)=0
This method registers the [Device](#) class method as a callback method to be called when a eventType occurs.
- virtual IpxCamErr [RegisterEvent](#) (uint32_t eventType, [IpxCam::EventCallback](#) *eventCallback, void *pPrivate)=0
RegisterEvent.
- virtual IpxCamErr [UnRegisterEvent2](#) (uint32_t eventType, [IpxCam::EventCallback2](#) *eventCallback, void *p↔Private)=0
This event occurs, when the camera was disconnected from the [System](#).
- virtual IpxCamErr [UnRegisterEvent](#) (uint32_t eventType, [IpxCam::EventCallback](#) *eventCallback, void *p↔Private)=0
UnRegisterEvent.

- virtual [lpxGenParam::Array](#) * [GetTransportParameters](#) (lpxCamErr *err=nullptr)=0
This method returns the transport parameters [lpxGenParam::Array](#) object of the camera device object.
- virtual [lpxGenParam::Array](#) * [GetCameraParameters](#) (lpxCamErr *err=nullptr)=0
This method returns the camera parameters [lpxGenParam::Array](#) object of the device object.
- virtual lpxCamErr [SaveConfiguration](#) (const char *fileName)=0
This method saves the camera parameters to the configuration file.
- virtual lpxCamErr [LoadConfiguration](#) (const char *fileName)=0
This method loads the configuration from file, and configures the camera with the parameter values, saved to this file.
- virtual [Endianness](#) [GetEndianness](#) () const =0
This method returns endianness of underlying protocol for this camera device.

Static Public Attributes

- static const uint32_t [CameraConnected](#) = 1003
This event occurs, if GenlCam event was triggered by the camera device.
- static const uint32_t [CameraDisconnected](#) = 1004
This event occurs, when the camera was connected to the [System](#).

7.6.1 Detailed Description

The [Device](#) class represents the device module in the GenTL module hierarchy.

This [Device](#) class provides methods to enable the communication and control of the Imperx device and enumerate/instantiate data stream objects. The methods can be used to enumerate and instantiate the Data [Stream](#) module objects. The device must correspond to the interface transport layer technology. For example, the device could be an Imperx GEV Camera and the transport layer technology would be GEV. The [Device](#) class can be used to retrieve data information about the device by returning the pointer to the [DeviceInfo](#) class. It can be used to retrieve the pointer to the [Stream](#) object and save / load the camera configurations to / from file.

7.6.2 Member Enumeration Documentation

7.6.2.1 enum lpxCam::Device::UploadEventType : uint32_t

Enumerator

- [FlashSectorErase](#)** Enum value FlashSectorErase.
- [FlashPageWrite](#)** Enum value FlashPagewrite.
- [FlashPageRead](#)** Enum value FlashPageRead.

7.6.2.2 enum lpxCam::Device::Endianness : uint8_t

An enum of endianness types of underlying protocol.

Enumerator

- [BigEndian](#)** Enum value Big-endian.
- [LittleEndian](#)** Enum value Little-endian

7.6.3 Constructor & Destructor Documentation

7.6.3.1 virtual IpxCam::Device::~Device () [inline],[virtual]

A destructor of the [Device](#) class.

Destructor. Destroys the [Device](#) and all its descendants.

7.6.4 Member Function Documentation

7.6.4.1 virtual uint32_t IpxCam::Device::GetNumStreams () [pure virtual]

This method retrieves the number of the data streams, provided by the [Device](#).

Returns

returns the number of the data streams

7.6.4.2 virtual Stream* IpxCam::Device::GetStreamByIndex (uint32_t idx = 0) [pure virtual]

This retrieves the pointer to the [Stream](#) object by stream index.

Parameters

in	<i>idx</i>	stream index value
----	------------	--------------------

Returns

Returns the pointer to the [Stream](#) object

7.6.4.3 virtual Stream* IpxCam::Device::GetStreamById (const char * id) [pure virtual]

This method retrieves the pointer to the [Stream](#) object by stream identifier.

Parameters

in	<i>id</i>	pointer to the string representing the stream identifier
----	-----------	--

Returns

Returns the pointer to the [Stream](#) object

7.6.4.4 `virtual DeviceInfo* IpxCam::Device::GetInfo () [pure virtual]`

This method returns a pointer to the [DeviceInfo](#) object , associated with the [Device](#).

Returns

Returns the pointer to the [DeviceInfo](#) object

7.6.4.5 `virtual IpxCamErr IpxCam::Device::ReadMem (uint64_t addr, void * data, size_t len) [pure virtual]`

This method reads a number of bytes from a given address of the [Device](#).

Parameters

in	<i>addr</i>	Byte address to read from
in	<i>data</i>	pointer to a user allocated byte data buffer
in	<i>len</i>	size of the amount of bytes to read from the register map address

Returns

Returns ErrorCode

7.6.4.6 `virtual IpxCamErr IpxCam::Device::WriteMem (uint64_t addr, const void * data, size_t len, size_t * written) [pure virtual]`

This method writes a number of bytes at a given address.

Parameters

in	<i>addr</i>	Byte address to read from
in	<i>data</i>	pointer to a user allocated byte data buffer
in	<i>len</i>	size of the amount of bytes to write to the register map address
out	<i>written</i>	size of bytes written

Returns

Returns ErrorCode

7.6.4.7 `virtual IpxCamErr IpxCam::Device::RegisterEvent2 (uint32_t eventType, IpxCam::EventCallback2 * eventCallback, void * pPrivate) [pure virtual]`

This method registers the [Device](#) class method as a callback method to be called when a eventType occurs.

Parameters

in	<i>eventType</i>	Event Type, can receive one of the following values: <ul style="list-style-type: none"> • GenICamEvent [1002] - this event occurs, if GenICam event was triggered by the camera • CameraConnected [1003] - this event occurs, when camera was connected to the System • CameraDisconnected [1004] - this event occurs, when camera was disconnected from the System
in	<i>eventCallback</i>	event CallBack
in	<i>pPrivate</i>	pointer to user's data

Returns

Returns Error code

7.6.4.8 `virtual IpxCamErr IpxCam::Device::RegisterEvent (uint32_t eventType, IpxCam::EventCallback * eventCallback, void * pPrivate) [pure virtual]`

RegisterEvent.

Deprecated Use [Device::RegisterEvent2](#) instead

7.6.4.9 `virtual IpxCamErr IpxCam::Device::UnRegisterEvent2 (uint32_t eventType, IpxCam::EventCallback2 * eventCallback, void * pPrivate) [pure virtual]`

This event occurs, when the camera was disconnected from the [System](#).

This method unregisters the [Interface](#) class callback method for the eventType.

Parameters

in	<i>eventType</i>	Event Type, can receive one of the following values: <ul style="list-style-type: none"> • GenICamEvent [1002] - this event occurs, if GenICam event was triggered by the camera • CameraConnected [1003] - this event occurs, when camera was connected to the System • CameraDisconnected [1004] - this event occurs, when camera was disconnected from the System
in	<i>eventCallback</i>	event CallBack
in	<i>pPrivate</i>	pointer to user's data

Returns

Returns Error code

```
7.6.4.10 virtual IpxCamErr IpxCam::Device::UnRegisterEvent ( uint32_t eventType, IpxCam::EventCallback * eventCallback,
void * pPrivate ) [pure virtual]
```

UnRegisterEvent.

Deprecated Use [Device::UnRegisterEvent2](#) instead

```
7.6.4.11 virtual IpxGenParam::Array* IpxCam::Device::GetTransportParameters ( IpxCamErr * err = nullptr ) [pure
virtual]
```

This method returns the transport parameters [IpxGenParam::Array](#) object of the camera device object.

Parameters

out	err	returns error code
-----	-----	--------------------

Returns

Returns the Transport parameters object pointer

```
7.6.4.12 virtual IpxGenParam::Array* IpxCam::Device::GetCameraParameters ( IpxCamErr * err = nullptr ) [pure
virtual]
```

This method returns the camera parameters [IpxGenParam::Array](#) object of the device object.

Parameters

out	err	returns error code
-----	-----	--------------------

Returns

Returns the Camera Parameters array object pointer

```
7.6.4.13 virtual IpxCamErr IpxCam::Device::SaveConfiguration ( const char * fileName ) [pure virtual]
```

This method saves the camera parameters to the configuration file.

Parameters

in	<i>fileName</i>	Configuration file name
----	-----------------	-------------------------

Returns

Returns Error code

7.6.4.14 `virtual IpxCamErr IpxCam::Device::LoadConfiguration (const char * fileName) [pure virtual]`

This method loads the configuration from file, and configures the camera with the parameter values, saved to this file.

Parameters

in	<i>fileName</i>	Configuration file name
----	-----------------	-------------------------

Returns

Returns Error code

7.6.4.15 `virtual Endianness IpxCam::Device::GetEndianness () const [pure virtual]`

This method returns endianness of underlying protocol for this camera device.

Returns

Returns endianness

The documentation for this class was generated from the following file:

- IpxCameraApi.h

7.7 IpxCam::DeviceInfo Class Reference

[DeviceInfo](#) class provides the information about the camera device.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~DeviceInfo](#) ()
DeviceInfo class destructor.
- virtual [Interface](#) * [GetInterface](#) ()=0
This method returns the interface of the device object.
- virtual const char * [GetID](#) ()=0
This method returns the unique device identifier string for the Imperx Camera device object.
- virtual const char * [GetVendor](#) ()=0
This method returns the vendor name of the camera device object.
- virtual const char * [GetModel](#) ()=0
This method returns the model name of the camera device object.
- virtual const char * [GetDisplayName](#) ()=0
This method returns the user readable display name of the Camera device object.
- virtual const char * [GetUserDefinedName](#) ()=0
This method returns the user defined name of the Camera device.
- virtual const char * [GetSerialNumber](#) ()=0
This method returns the serial number of the Camera device .
- virtual const char * [GetVersion](#) ()=0
This method returns the device version of the device object.
- virtual int32_t [GetAccessStatus](#) ()=0
Returns the device access status.
- virtual const char * [GetUSB3HostInfo](#) ()=0
Returns the information about USB3 host controller.
- virtual const char * [GetIPAddress](#) (lpxCamErr *err)=0
Returns the IP address of the GEV camera.
- virtual const char * [GetIPMask](#) (lpxCamErr *err)=0
Returns the IP subnet mask of the GEV camera.
- virtual const char * [GetIPGateway](#) (lpxCamErr *err)=0
Returns the IP gateway of GEV camera.
- virtual lpxCamErr [GetIP](#) (uint32_t *addr, uint32_t *netmask, uint32_t *gateway)=0
Gets IP information from the GEV camera.
- virtual lpxCamErr [ForceIP](#) (const char *addr, const char *netmask, const char *gateway)=0
Set the IP address to GEV camera.
- virtual lpxCamErr [ForceIP](#) (uint32_t addr, uint32_t netmask, uint32_t gateway)=0
Set IP address to GEV camera.

7.7.1 Detailed Description

[DeviceInfo](#) class provides the information about the camera device.

The [DeviceInfo](#) class can be used to retrieve the information about the device, and to create the [lpxCam::Device](#) object by [lpxCam_CreateDevice\(\)](#) call

7.7.2 Constructor & Destructor Documentation

7.7.2.1 `virtual IpxCam::DeviceInfo::~~DeviceInfo () [inline],[virtual]`

[DeviceInfo](#) class destructor.

Destroys the [DeviceInfo](#) object and all its descendants.

7.7.3 Member Function Documentation

7.7.3.1 `virtual Interface* IpxCam::DeviceInfo::GetInterface () [pure virtual]`

This method returns the interface of the device object.

Returns the [IpxCam::Interface](#) object pointer for the camera device, associated with the [DeviceInfo](#) object

Returns

Returns the [Interface](#)

7.7.3.2 `virtual const char* IpxCam::DeviceInfo::GetID () [pure virtual]`

This method returns the unique device identifier string for the Imperx Camera device object.

Returns

Returns the unique device identifier string for the Imperx Camera device

7.7.3.3 `virtual const char* IpxCam::DeviceInfo::GetVendor () [pure virtual]`

This method returns the vendor name of the camera device object.

Returns

Returns the camera device vendor name

7.7.3.4 `virtual const char* IpxCam::DeviceInfo::GetModel () [pure virtual]`

This method returns the model name of the camera device object.

Returns

Returns the Camera device model name

7.7.3.5 `virtual const char* IpxCam::DeviceInfo::GetDisplayName () [pure virtual]`

This method returns the user readable display name of the Camera device object.

Returns

Returns the name of the Camera device

7.7.3.6 `virtual const char* IpxCam::DeviceInfo::GetUserDefinedName () [pure virtual]`

This method returns the user defined name of the Camera device.

Returns

Returns the user defined name of the Camera device

7.7.3.7 `virtual const char* IpxCam::DeviceInfo::GetSerialNumber () [pure virtual]`

This method returns the serial number of the Camera device .

Returns

Returns the serial number of the Camera device

7.7.3.8 `virtual const char* IpxCam::DeviceInfo::GetVersion () [pure virtual]`

This method returns the device version of the device object.

Returns

Returns the [Device](#) version

7.7.3.9 `virtual int32_t IpxCam::DeviceInfo::GetAccessStatus () [pure virtual]`

Returns the device access status.

This method returns the information about the current access status of the Camera device

Returns

Status Access Code, can receive one of the following values:

- **AccessStatusUnknown** [0] - The current availability of the device is unknown.
- **AccessStatusReadWrite** [1] - The device is available for Read/Write access
- **AccessStatusReadOnly** [2] - The device is available for Read only access
- **AccessStatusNoAccess** [3] - The device is not available either because it is already open or because it is not reachable.
- **IpSubnetMismatch** [1001] - The device is available, but IP address does not match to the host subnet mask.

7.7.3.10 `virtual const char* IpxCam::DeviceInfo::GetUSB3HostInfo () [pure virtual]`

Returns the information about USB3 host controller.

This method returns the information about USB3 host controller where the camera device is connected to.

Returns

Returns the pointer to string structure or nullptr for non-USB camera

7.7.3.11 `virtual const char* IpxCam::DeviceInfo::GetIPAddress (IpxCamErr * err) [pure virtual]`

Returns the IP address of the GEV camera.

This method returns the IP address of the GEV camera, retrieved from DISCOVERY_ACK packet, received from the camera device

Parameters

out	<i>err</i>	Error code
-----	------------	------------

Returns

Returns IP Address string or nullptr for non-GEV camera

7.7.3.12 `virtual const char* IpxCam::DeviceInfo::GetIPMask (IpxCamErr * err) [pure virtual]`

Returns the IP subnet mask of the GEV camera.

This method returns the IP subnet mask of the GEV camera, retrieved from DISCOVERY_ACK packet, received from the camera device

Parameters

out	<i>err</i>	Error code
-----	------------	------------

Returns

Returns IP subnet mask string or nullptr for non-GEV camera

7.7.3.13 `virtual const char* IpxCam::DeviceInfo::GetIPGateway (IpxCamErr * err) [pure virtual]`

Returns the IP gateway of GEV camera.

This method returns the IP gateway of the GEV camera, retrieved from DISCOVERY_ACK packet, received from the camera device

Parameters

out	<i>err</i>	Error code
-----	------------	------------

Returns

Returns IP gateway string or nullptr for non-GEV camera

7.7.3.14 `virtual IpxCamErr IpxCam::DeviceInfo::GetIP (uint32_t * addr, uint32_t * netmask, uint32_t * gateway)` [pure virtual]

Gets IP information from the GEV camera.

This method returns the IP address, netmask, and gateway of the GEV camera, from DISCOVERY_ACK packet, received from the camera

Parameters

out	<i>addr</i>	IP Address
out	<i>netmask</i>	IP Address subnet mask
out	<i>gateway</i>	Gateway address

Returns

Returns Error code

7.7.3.15 `virtual IpxCamErr IpxCam::DeviceInfo::ForceIP (const char * addr, const char * netmask, const char * gateway)` [pure virtual]

Set the IP address to GEV camera.

This method sets the specified IP address to the GEV camera, using ForceIP GVCP command

Parameters

in	<i>addr</i>	IP Address string to set
in	<i>netmask</i>	IP Address subnet mask string
in	<i>gateway</i>	Gateway address string

Returns

Returns Error code

7.7.3.16 `virtual IpxCamErr IpxCam::DeviceInfo::ForceIP (uint32_t addr, uint32_t netmask, uint32_t gateway)` [pure virtual]

Set IP address to GEV camera.

This method sets the specified IP address to the GEV camera, using ForceIP GVCP command

Parameters

in	<i>addr</i>	IP Address to set (host byte order)
in	<i>netmask</i>	IP Address subnet mask (host byte order)
in	<i>gateway</i>	Gateway address (host byte order)

Returns

Returns Error code

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.8 IpxGenParam::Enum Class Reference

A class containing methods for Enumeration GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Enum:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [Enum](#) type.
- virtual [size_t](#) [GetEnumEntriesCount](#) ([IpxCamErr](#) *err=nullptr)=0
This method gets the number of entry nodes.
- virtual [EnumEntry](#) * [GetEnumEntryByIndex](#) ([size_t](#) aIndex)=0
This method gets the [Enum](#) Entry node by the Index number.
- virtual [EnumEntry](#) * [GetEnumEntryByName](#) (const char *name)=0
This method gets the [Enum](#) Entry node by Name.
- virtual [EnumEntry](#) * [GetEnumEntryByValue](#) ([int64_t](#) val)=0
This method gets the [Enum](#) Entry node by Value.
- virtual [int64_t](#) [GetValue](#) ([IpxCamErr](#) *err=nullptr)=0
This method gets the [Enum](#) Entry node value as Integer.
- virtual const char * [GetValueStr](#) ([IpxCamErr](#) *err=nullptr)=0
This method gets the [Enum](#) Entry node value as [String](#).
- virtual [IpxCamErr](#) [SetValue](#) ([int64_t](#) val)=0
This method sets the [Enum](#) Entry node value as Integer.
- virtual [IpxCamErr](#) [SetValueStr](#) (const char *val)=0
This method sets the [Enum](#) Entry node as [String](#).

7.8.1 Detailed Description

A class containing methods for Enumeration GenICam camera parameter.

A class containing methods to access the Enumeration GenICam camera parameter, using Integer or [String](#) value.

For example, the picture below illustrates the enumeration "WhiteBalanceMode".

7.8.2 Member Function Documentation

7.8.2.1 virtual [ParamType](#) [IpxGenParam::Enum::GetType](#) () [inline],[virtual]

This method returns the node object [Enum](#) type.

Returns

If the method succeeds, it will returns the [Enum](#) parameter type.

Implements [IpxGenParam::Param](#).

7.8.2.2 virtual [size_t](#) [IpxGenParam::Enum::GetEnumEntriesCount](#) ([IpxCamErr](#) * err = nullptr) [pure virtual]

This method gets the number of entry nodes.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the number of EnumEntries • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	-----	---

Returns

Returns the number of enum entry nodes.

7.8.2.3 `virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByIndex (size_t aIndex) [pure virtual]`

This method gets the [Enum](#) Entry node by the Index number.

Parameters

in	<i>aIndex</i>	Index number
----	---------------	--------------

Returns

If the method succeeds, it returns the [Enum](#) Entry node.

7.8.2.4 `virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByName (const char * name) [pure virtual]`

This method gets the [Enum](#) Entry node by Name.

Parameters

in	<i>name</i>	Entry Name
----	-------------	------------

Returns

If the method succeeds, it returns the [Enum](#) Entry node.

7.8.2.5 `virtual EnumEntry* IpxGenParam::Enum::GetEnumEntryByValue (int64_t val) [pure virtual]`

This method gets the [Enum](#) Entry node by Value.

Parameters

in	val	Entry Value
----	-----	-------------

Returns

If the method succeeds, it returns the [Enum](#) Entry node.

7.8.2.6 `virtual int64_t IpxGenParam::Enum::GetValue (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [Enum](#) Entry node value as Integer.

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Enum Entry node value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	---

Returns

If the method succeeds, it returns the [Enum](#) Entry node value.

7.8.2.7 `virtual const char* IpxGenParam::Enum::GetValueStr (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [Enum](#) Entry node value as [String](#).

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully get the Enum Entry node string • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	---

Returns

If the method succeeds, it returns the [Enum](#) Entry node string.

7.8.2.8 `virtual IpxCamErr IpxGenParam::Enum::SetValue (int64_t val) [pure virtual]`

This method sets the [Enum](#) Entry node value as Integer.

Parameters

in	val	Enum Entry node value
----	-----	---------------------------------------

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Enum](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type

7.8.2.9 `virtual IpxCamErr IpxGenParam::Enum::SetValueStr (const char * val) [pure virtual]`

This method sets the [Enum](#) Entry node as [String](#).

Parameters

in	val	Enum Entry node String
----	-----	--

Returns

Returns the error code

The documentation for this class was generated from the following file:


- `IpxCameraApi.h`

7.9 IpxGenParam::EnumEntry Class Reference

[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::EnumEntry:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [EnumEntry](#) type.
- virtual int64_t [GetValue](#) (IpxCamErr *err=nullptr)=0
This method gets the [EnumEntry](#) numerical value.
- virtual const char * [GetValueStr](#) (IpxCamErr *err=nullptr)=0
This method gets the [EnumEntry](#) String value.

7.9.1 Detailed Description

[EnumEntry](#) class represents the entry of GenICam [Enum](#) parameter.

A Class for GenICam [Enum](#) Entries has methods to access the Enumeration GenICam parameter entry.

For example, the mapping below illustrates entries of the IEnumeration interface for the AOI2_Select feature. This feature can select the mode of operation for Slave AOI #2. The enumeration entries could be "Off", "Include", and "Exclude".

7.9.2 Member Function Documentation

7.9.2.1 virtual ParamType IpxGenParam::EnumEntry::GetType () [inline],[virtual]

This method returns the node object [EnumEntry](#) type.

Returns

If the method succeeds, it returns the ParamType object type of the [EnumEntry](#).

Implements [IpxGenParam::Param](#).

7.9.2.2 virtual int64_t IpxGenParam::EnumEntry::GetValue (IpxCamErr * err = nullptr) [pure virtual]

This method gets the [EnumEntry](#) numerical value.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • IpxCamErr::IPX_CAM_ERR_OK - Successfully indicates EnumEntry value was retrieved • IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR - Unable to access genicam specified node • IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR - Unable to access genicam specified node type
-----	-----	---

Returns

If the method succeeds, it returns the value read of the [EnumEntry](#).

7.9.2.3 `virtual const char* IpxGenParam::EnumEntry::GetValueStr (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [EnumEntry String](#) value.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • IpxCamErr::IPX_CAM_ERR_OK - Successfully indicates EnumEntry string value was retrieved • IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR - Unable to access genicam specified node • IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR - Unable to access genicam specified node type
-----	-----	--

Returns

If the method succeeds, it returns the [String](#) value read of the [EnumEntry](#).

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.10 IpxGenParam::Float Class Reference

A class containing methods for [Float](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Float:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [Float](#) type.
- virtual IpxCamErr [SetValue](#) (double val)=0
This method sets the node value.
- virtual double [GetValue](#) (IpxCamErr *err=nullptr)=0
This method gets the [Float](#) node value.
- virtual double [GetMin](#) (IpxCamErr *err=nullptr)=0
This method gets the minimum value.
- virtual double [GetMax](#) (IpxCamErr *err=nullptr)=0
This method gets the maximum value.
- virtual const char * [GetUnit](#) (IpxCamErr *err=nullptr)=0
This method gets the Unit.

7.10.1 Detailed Description

A class containing methods for [Float](#) GenICam camera parameter.

A class containing methods to access the [Float](#) GenICam camera parameter as floating point value.

For example, the picture below illustrates the float "ExposureTime".

7.10.2 Member Function Documentation

7.10.2.1 virtual [ParamType](#) IpxGenParam::Float::GetType () [inline], [virtual]

This method returns the node object [Float](#) type.

Returns

Returns the parameter type

Implements [IpxGenParam::Param](#).

7.10.2.2 `virtual IpxCamErr IpxGenParam::Float::SetValue (double val) [pure virtual]`

This method sets the node value.

Parameters

in	<i>val</i>	The value to set
----	------------	------------------

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Float](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.10.2.3 `virtual double IpxGenParam::Float::GetValue (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the [Float](#) node value.

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully get the Float value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	--

Returns

Gets the [Float](#) node value

7.10.2.4 `virtual double IpxGenParam::Float::GetMin (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the minimum value.

Parameters

<i>out</i>	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Minimum float value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
------------	------------	---

Returns

Returns the minimum

7.10.2.5 `virtual double IpxGenParam::Float::GetMax (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the maximum value.

Parameters

<i>out</i>	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Maximum float value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
------------	------------	---

Returns

Returns the maximum

7.10.2.6 `virtual const char* IpxGenParam::Float::GetUnit (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the Unit.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the units • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	-----	---

Returns

Returns the measurement unit string

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

7.11 IpxGui::IpxGenParamTreeView Class Reference

[IpxGenParamTreeView](#) class represents the GenICam parameters node tree panel.

```
#include <IpxCameraGuiApi.h>
```

Public Member Functions

- virtual [~IpxGenParamTreeView](#) ()
A destructor of the [IpxGenParamTreeView](#) class.
- virtual void [setParams](#) ([IpxGenParam::Array](#) *genParam)=0
Sets the [IpxGenParam::Array](#) object to the node tree GUI.
- virtual void [setParams](#) (`IPX_GENAPI_NS::INodeMap` *nodemap)=0
Sets the [GenApi::INodeMap](#) object to the node tree GUI.
- virtual void [clearParams](#) ()=0
Clears the parameters of the node tree GUI.
- virtual [Visibility](#) [visibility](#) () const =0
This method returns the current visibility mode.
- virtual void [setVisibility](#) ([Visibility](#) [visibility](#))=0
This method sets visibility mode.
- virtual const char * [saveState](#) () const =0
Saves the current state of the Tree View.
- virtual void [loadState](#) (const char *state)=0
Loads the state of the Tree View.
- virtual void [setPollingTime](#) (`uint64_t` pollingTime)=0
Sets the polling time.
- virtual `uint64_t` [getPollingTime](#) ()=0
Retrieves current polling time.
- virtual void [enablePolling](#) (bool enable)=0
Enables the polling.
- virtual bool [isPollingEnabled](#) ()=0
Retrieves current polling state.

7.11.1 Detailed Description

[IpxGenParamTreeView](#) class represents the GenICam parameters node tree panel.

The [IpxGenParamTreeView](#) class is composed of functions to set and clear parameters of the GenICam parameters node tree of the camera. The node tree can be set with the current parameters stored in the [IpxGenParam::Array](#) and [GenApi::INodeMap](#) class.

For example, we can declare the instance of [IpxGui::IpxGenParamTreeView](#) class as `m_parameterView` as shown below:

```
IpxGui::IpxGenParamTreeView* m_ParameterView;
```


7.11.2 Constructor & Destructor Documentation

7.11.2.1 `virtual IpxGui::IpxGenParamTreeView::~~IpxGenParamTreeView () [inline], [virtual]`

A destructor of the [IpxGenParamTreeView](#) class.

Destroys the [IpxGenParamTreeView](#) object and all its descendants.

Here is the call graph for this function:



7.11.3 Member Function Documentation

7.11.3.1 `virtual void IpxGui::IpxGenParamTreeView::setParams (IpxGenParam::Array * genParam)` [pure virtual]

Sets the `IpxGenParam::Array` object to the node tree GUI.

This method sets the parameters of the node tree by the information extracted from the `IpxGenParam::Array` class

Parameters

in	<i>genParam</i>	The pointer to the IpxGenParam::Array class.
----	-----------------	--

Returns

void

For example, set the Camera Parameters to the corresponding fields of the TreeView as shown below:

```
// Establish camera device
m_camera = IpxCam_CreateDevice(m_devInfo);

// If the camera exist, set the camera parameter to the corresponding fields of the GUI TreeView
if(m_camera){
    m_ParameterView->setParams(m_camera->GetCameraParameters());
}
```

7.11.3.2 `virtual void IpxGui::IpxGenParamTreeView::setParams (IPX_GENAPI_NS::INodeMap * nodemap)` [pure virtual]

Sets the GenApi::INodeMap object to the node tree GUI.

This method sets the parameters of the node tree with parameters retrieved from the GenApi::INodeMap class. The INodeMap consists of a list of nodes representing the GenICam compliant camera high-level features.

Parameters

in	<i>nodemap</i>	The pointer to the GenApi::INodeMap class.
----	----------------	--

Returns

Void.

For example, setting the parameters of the node map.

```
// Instantiate the IpxGui::IpxGenParamTreeView
IpxGui::IpxGenParamTreeView* m_ParameterView;
...
auto params = GetCameraParameters(&retErr);
if(!params) {
    return retErr;
}
GenApi::INodeMap *nodemap = param->GetNodeMap(&retErr);
if(!nodemap){
    return retErr;
}
...
// Set the nodemap parameters of the GUI TreeView
m_ParameterView->setParams(nodemap);
...
```

7.11.3.3 virtual void IpxGui::IIPxGenParamTreeView::clearParams () [pure virtual]

Clears the parameters of the node tree GUI.

This method clears the parameters of the node tree that have been set by the instance of the [IpxGui::IIPxGenParamTreeView](#) class

Returns

void.

For example, clear all the parameters after we disconnect the camera as shown below:

```
// Instantiate the IpxGui::IIPxGenParamTreeView
IpxGui::IIPxGenParamTreeView* m_ParameterView;

// Connect the camera
...
// Set some camera parameters
...
// Perform some actions
...
// Clear parameters during disconnecting process of camera
m_ParameterView->clearParam();
```

7.11.3.4 virtual Visibility IpxGui::IIPxGenParamTreeView::visibility () const [pure virtual]

This method returns the current visibility mode.

This method retrieves the current setting of the user visibility level for the feature

Returns

Visibility value

7.11.3.5 virtual void IpxGui::IIPxGenParamTreeView::setVisibility (Visibility visibility) [pure virtual]

This method sets visibility mode.

It sets the current visibility level for the feature.

Parameters

in	<i>visibility</i>	The visibility mode value to set
----	-------------------	----------------------------------

Returns

Void.

7.11.3.6 `virtual const char* lpxGui::lpxGenParamTreeView::saveState () const` [pure virtual]

Saves the current state of the Tree View.

This method creates the string, representing the current state of the Tree View, and returns the pointer to this string.

Returns

If succeeds, the method returns pointer to the state string. Otherwise, the return value is nullptr. The string consists of sub-string values separated by the token. Just save this data somewhere if you want to restore the state later.

7.11.3.7 `virtual void lpxGui::lpxGenParamTreeView::loadState (const char * state)` [pure virtual]

Loads the state of the Tree View.

This method loads the state of the Tree View using the string, created by [saveState\(\)](#) method. The individual node can be in expanded or collapse state.

Parameters

in	<i>state</i>	State string to be loaded. The string consists of sub-string values separated by the token.
----	--------------	---

7.11.3.8 `virtual void lpxGui::lpxGenParamTreeView::setPollingTime (uint64_t pollingTime)` [pure virtual]

Sets the polling time.

This method sets the value of the parameters pooling time. Polling should be enabled by [enablePolling\(\)](#) function

Parameters

in	<i>pollingTime</i>	time in msec to be set
----	--------------------	------------------------

7.11.3.9 `virtual uint64_t lpxGui::lpxGenParamTreeView::getPollingTime ()` [pure virtual]

Retrieves current polling time.

This method retrieves the value of the parameters polling time. Polling should be enabled by [enablePolling\(\)](#) function

Returns

current polling time in msec

The documentation for this class was generated from the following file:


- lpxCameraGuiApi.h

7.12 IpxGenParam::Int Class Reference

A class containing methods for Integer GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Int:



Public Member Functions

- virtual [ParamType GetType](#) ()
This method returns the node object [Int](#) type.
- virtual IpxCamErr [SetValue](#) (int64_t val)=0
This method sets the [Int](#) node value.
- virtual int64_t [GetValue](#) (IpxCamErr *err=nullptr)=0
This method gets the [Int](#) node value.
- virtual int64_t [GetMin](#) (IpxCamErr *err=nullptr)=0
This method gets the minimum value.
- virtual int64_t [GetMax](#) (IpxCamErr *err=nullptr)=0
This method gets the maximum value.
- virtual int64_t [GetIncrement](#) (IpxCamErr *err=nullptr)=0
This method gets the Increment value.

7.12.1 Detailed Description

A class containing methods for Integer GenICam camera parameter.

A class containing methods to access the Integer GenICam camera parameter as integer value.

For example, the mapping below illustrates "Width" Integer parameter.

7.12.2 Member Function Documentation

7.12.2.1 virtual ParamType IpxGenParam::Int::GetType () [inline],[virtual]

This method returns the node object [Int](#) type.

Returns

Returns the parameter type

Implements [IpxGenParam::Param](#).

7.12.2.2 virtual IpxCamErr IpxGenParam::Int::SetValue (int64_t val) [pure virtual]

This method sets the [Int](#) node value.

Parameters

in	val	Int node value
----	-----	--------------------------------

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the [Int](#) value
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type
- `IpxCamErr::IPX_CAM_GENICAM_OUT_OF_RANGE` - the value entered is out of range

7.12.2.3 virtual int64_t IpxGenParam::Int::GetValue (IpxCamErr * err = nullptr) [pure virtual]

This method gets the [Int](#) node value.

Parameters

out	err	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Int value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	-----	---

Returns

Returns the [Int](#) node value

7.12.2.4 `virtual int64_t IpxGenParam::Int::GetMin (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the minimum value.

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Minimum int value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	---

Returns

Returns the minimum

7.12.2.5 `virtual int64_t IpxGenParam::Int::GetMax (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the maximum value.

Parameters

out	<i>err</i>	returns error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the Maximum int value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	------------	---

Returns

Returns the maximum

7.12.2.6 `virtual int64_t IpxGenParam::Int::GetIncrement (IpxCamErr * err = nullptr) [pure virtual]`

This method gets the Increment value.

Parameters

out	err	returns error code : <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the increment value • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type
-----	-----	--

Returns

Returns the increment

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

7.13 IpxCam::Interface Class Reference

The [Interface](#) class represents a interface module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~Interface](#) ()
Interface class destructor.
- virtual [DeviceInfoList](#) * [GetDeviceInfoList](#) ()=0
This method retrieves the list of [DeviceInfo](#) objects for the camera devices, available on this [Interface](#).
- virtual [DeviceInfo](#) * [GetFirstDeviceInfo](#) ()=0
This method retrieves the [DeviceInfo](#) object for the first device available on this [Interface](#).
- virtual [DeviceInfo](#) * [GetDeviceInfoById](#) (const char *deviceId)=0
This method retrieves the [DeviceInfo](#) object pointer for the specified device identifier.
- virtual `IpxCamErr` [ReEnumerateDevices](#) (bool *pChanged, uint64_t iTimeout)=0
This method re-enumerates the devices.
- virtual const char * [GetDescription](#) ()=0
This method returns the description of the interface.
- virtual [InterfaceType](#) [GetType](#) ()=0
This method gets the type of interface.
- virtual const char * [GetId](#) ()=0
This method gets the identifier of the interface .
- virtual const char * [GetVersion](#) ()=0

This method gets the version of [Interface](#) driver.

- virtual lpxCamErr [RegisterEvent2](#) (uint32_t eventType, [lpxCam::EventCallback2](#) *eventCallback, void *pPrivate)=0

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

- virtual lpxCamErr [RegisterEvent](#) (uint32_t eventType, [lpxCam::EventCallback](#) *eventCallback, void *pPrivate)=0

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

- virtual lpxCamErr [UnRegisterEvent2](#) (uint32_t eventType, [lpxCam::EventCallback2](#) *eventCallback, void *pPrivate)=0

This method unregisters the [Interface](#) class callback method for the eventType.

- virtual lpxCamErr [UnRegisterEvent](#) (uint32_t eventType, [lpxCam::EventCallback](#) *eventCallback, void *pPrivate)=0

This method unregisters the [Interface](#) class callback method for the eventType.

- virtual [lpxGenParam::Array](#) * [GetParameters](#) (lpxCamErr *err=nullptr)=0

This method returns the parameter array used to control the Imperx Camera device.

- virtual [Device](#) * [CreateDeviceFromConfig](#) (const char *fileName, lpxCamErr *err=nullptr)=0

Creates the [Device](#) object from configuration file.

7.13.1 Detailed Description

The [Interface](#) class represents a interface module in the GenTL module hierarchy.

This class represents an individual physical interface in the [System](#). For example, a network interface card (NIC) for GigE Vision connection, CXP or Camera Link frame grabber board, or USB3 Vision driver in the GenTL system. The [Interface](#) class includes methods to enumerate the available devices on the physical interface in the system.

7.13.2 Constructor & Destructor Documentation

7.13.2.1 virtual lpxCam::Interface::~Interface () [inline],[virtual]

[Interface](#) class destructor.

Destroys the [Interface](#) object and all its descendants.

7.13.3 Member Function Documentation

7.13.3.1 virtual DeviceInfoList* lpxCam::Interface::GetDeviceInfoList () [pure virtual]

This method retrieves the list of [DeviceInfo](#) objects for the camera devices, available on this [Interface](#).

Returns

Returns the pointer to DeviceInfoList object

For example,

```
// Get the Device Info List for the Interface
// List has to be released, let us use unique pointer
auto del = [](IpxCam::DeviceInfoList *l) { l->Release(); };
std::unique_ptr<IpxCam::DeviceInfoList, decltype(del)> list(iface->GetDeviceInfoList(), del);

if (list->GetCount() == 0)
{
    std::cout << "No Interface Available. " << endl;
    exit(1);
}

IpxCam::Device *device = nullptr;
for (auto devInfo = list->GetFirst(); devInfo; devInfo = list->GetNext())
{
    if (std::string("Test camera") == devInfo->GetModel())
    {
        device = IpxCam::IpxCam_CreateDevice(devInfo);
        break;
    }
}
```

7.13.3.2 virtual DeviceInfo* IpxCam::Interface::GetFirstDeviceInfo () [pure virtual]

This method retrieves the [DeviceInfo](#) object for the first device available on this [Interface](#).

Returns

Returns the pointer to [DeviceInfo](#) object or nullptr if no device found

For example,

```
//Retrieve the first device available for the specified interface.
lDeviceInfo = iface->GetFirstDeviceInfo();

std::cout << "First Device Info ModelName" << lDeviceInfo->GetModel() << endl;
```

7.13.3.3 virtual DeviceInfo* IpxCam::Interface::GetDeviceInfoById (const char * deviceId) [pure virtual]

This method retrieves the [DeviceInfo](#) object pointer for the specified device identifier.

Parameters

in	<i>deviceId</i>	Device identifier
----	-----------------	-----------------------------------

Returns

Returns the pointer to [DeviceInfo](#) object or nullptr if no such device found

7.13.3.4 `virtual lpxCamErr lpxCam::Interface::ReEnumerateDevices (bool * pChanged, uint64_t iTimeout)` [pure virtual]

This method re-enumerates the devices.

The ReEnumerateDevices method allows the user to re-enumerate the devices connected to the [Interface](#) and update the DeviceInfoList object returned by subsequent [GetDeviceInfoList\(\)](#) method calls.

Parameters

in	<i>pChanged</i>	Change in Device
in	<i>iTimeout</i>	Timeout allowed to search for available camera devices

Returns

Returns error code

7.13.3.5 `virtual const char* lpxCam::Interface::GetDescription ()` [pure virtual]

This method returns the description of the interface.

The GetDescription method gets the user readable string description of the interface.

Returns

Returns the Description of the interface

7.13.3.6 `virtual InterfaceType lpxCam::Interface::GetType ()` [pure virtual]

This method gets the type of interface.

The GetType method returns the [Interface](#) Type (Transport Layer Technology) of this interface object

Returns

Returns [Interface](#) Type

The interface type return can be the following:

```
enum InterfaceType
{
    USB3Vision    = 1,
    GigEVision    = 2,
    CameraLink    = 3,
    CoaxPress     = 4,
    HdSdi         = 5,
    AllInterfaces = 0xff,
};
```

7.13.3.7 `virtual const char* lpxCam::Interface::GetId () [pure virtual]`

This method gets the identifier of the interface .

The GetId method returns the interface identifier that could be used to instantiate the interface object

Returns

Returns interface identifier

7.13.3.8 `virtual const char* lpxCam::Interface::GetVersion () [pure virtual]`

This method gets the version of [Interface](#) driver.

Returns the pointer to the string with the version of the interface driver

Returns

Returns the version of the interface driver

7.13.3.9 `virtual lpxCamErr lpxCam::Interface::RegisterEvent2 (uint32_t eventType, lpxCam::EventCallback2 * eventCallback, void * pPrivate) [pure virtual]`

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

Parameters

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	pointer to event CallBack method
in	<i>pPrivate</i>	pointer to user's data

Returns

Returns Error code

7.13.3.10 `virtual lpxCamErr lpxCam::Interface::RegisterEvent (uint32_t eventType, lpxCam::EventCallback * eventCallback, void * pPrivate) [pure virtual]`

This method registers the [Interface](#) class method as a callback method to be called when a eventType occurs.

Deprecated Use RegisterEvent2 instead

7.13.3.11 `virtual IpxCamErr IpxCam::Interface::UnRegisterEvent2 (uint32_t eventType, IpxCam::EventCallback2 * eventCallback, void * pPrivate) [pure virtual]`

This method unregisters the [Interface](#) class callback method for the *eventType*.

Parameters

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	pointer to event CallBack method
in	<i>pPrivate</i>	pointer to user's data

Returns

Returns Error code

7.13.3.12 `virtual IpxCamErr IpxCam::Interface::UnRegisterEvent (uint32_t eventType, IpxCam::EventCallback * eventCallback, void * pPrivate) [pure virtual]`

This method unregisters the [Interface](#) class callback method for the *eventType*.

Deprecated Use UnRegisterEvent2 instead

7.13.3.13 `virtual IpxGenParam::Array* IpxCam::Interface::GetParameters (IpxCamErr * err = nullptr) [pure virtual]`

This method returns the parameter array used to control the Imperx Camera device.

Parameters

out	<i>err</i>	returns error code
-----	------------	--------------------

Returns

Returns the pointer to [IpxGenParam::Array](#) object, used to control the Imperx Camera device

7.13.3.14 `virtual Device* IpxCam::Interface::CreateDeviceFromConfig (const char * fileName, IpxCamErr * err = nullptr) [pure virtual]`

Creates the [Device](#) object from configuration file.

This method creates, configures and sets up the device using the information retrieved from the specified configuration file

Parameters

in	<i>fileName</i>	Configuration file to open
out	<i>err</i>	returns error code

Returns

Returns [Device](#) or nullptr if device cannot be instantiated

The documentation for this class was generated from the following file:

- [IpxCameraApi.h](#)

7.14 IpxCam::List< _T > Class Template Reference

The [List](#) class is used as list-like container for the specified template type objects.

```
#include <IpxCameraApi.h>
```

Public Types

- typedef [_T](#) [elem_type](#)

Public Member Functions

- virtual [~List](#) ()
A destructor of the [List](#) class.
- virtual void [Release](#) ()=0
This method releases the instance of the list of the specified object.
- virtual size_t [GetCount](#) ()=0
This functions gets the number of items in the specified list object.
- virtual [elem_type](#) * [GetFirst](#) ()=0
This method retrieves the first element in the specified list object.
- virtual [elem_type](#) * [GetNext](#) ()=0
This method retrieves the next element in the specified list object.

7.14.1 Detailed Description

```
template<class _T>
class IpxCam::List< _T >
```

The [List](#) class is used as list-like container for the specified template type objects.

The supported template type objects are [Interface](#), [Device](#), [DeviceInfo](#), [Stream](#), and [Buffer](#).

They can be declared as follows:

IpxCam::List<Interface> *interfaceList	This class represents the list of Interface objects.
IpxCam::List<Device> *deviceList	This class represents the list of Device objects.
IpxCam::List<DeviceInfo> *deviceInfoList	This class represents the list of DeviceInfo objects.
IpxCam::List<Stream> *streamList	This class represents the list of Data Stream objects
IpxCam::List<Buffer> *bufferList	This class represents the list of Buffer objects

Alternatively, you can also use the declared typedef (aliases for specific objects) provided in the [IpxCam](#) namespace as shown below:

```
typedef List<Interface>    InterfaceList;
typedef List<DeviceInfo>   DeviceInfoList;
typedef List<Device>      DeviceList;
```

They can be declared as follows:

InterfaceList *interfaceList	This class represents the list of Interface objects.
DeviceInfoList *deviceInfoList	This class represents the list of DeviceInfo objects.

This class can be used to search through the list of objects discovered.

Example using DeviceInfoList

In this example, you will see how to use the DeviceInfoList. An example is shown below that demonstrates on how to use the list class methods. The **deviceInfoList->GetCount()** method is used retrieve the number of devices connected. We confirm that at least one device is available. Next, the for loop will loop from the first device information listed using the **deviceInfoList->GetFirst()** function to the end of the list. During each iteration the **deviceInfoList->GetNext()** will increment to the next deviceInfo available. In the example, you will notice that we search for a specified device model name. Once, the specified device is found, we will release the **deviceInfoList->Release()** and the create the specified device using the **IpxCam::IpxCam_CreateDevice()** method.

```
// Get the Device Info List for the Interface
// List has to be released, let us use unique pointer
auto del = [](IpxCam::DeviceInfoList *l) { l->Release(); };
std::unique_ptr<IpxCam::DeviceInfoList, decltype(del)> list(iface->GetDeviceInfoList(), del);

if (list->GetCount() == 0)
{
    std::cout << "No Interface Available. " << endl;
    exit(1);
}

IpxCam::Device *device = nullptr;
for (auto devInfo = list->GetFirst(); devInfo; devInfo = list->GetNext())
{
    if (std::string("Test camera") == devInfo->GetModel())
    {
        device = IpxCam::IpxCam_CreateDevice(devInfo);
        break;
    }
}
```

Example using InterfaceList

In this example, you will see how to use the InterfaceList. You will retrieve the interfaces available for this system. Next, the for loop will loop from the first interface available using the **list->GetFirst()** method to the end of the list. During each iteration the **list->GetNext()** will increment to the next interface available.

```
// Used later to get chosen interface
std::vector<IpxCam::Interface*> ifaceVector;

// Get the Interface List for the System
auto list = system->GetInterfaceList();

// Get the individual Interface elements
for (auto iface = list->GetFirst(); iface; iface = list->GetNext())
{
    ifaceVector.push_back(iface);

    // Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->GetDescription() << "Id " << iface
        ->GetId() << endl;
}

// List has to be released
list->Release();
```

7.14.2 Member Typedef Documentation

7.14.2.1 `template<class _T> typedef _T IpxCam::List<_T>::elem_type`

Element Type

7.14.3 Constructor & Destructor Documentation

7.14.3.1 `template<class _T> virtual IpxCam::List<_T>::~~List() [inline],[virtual]`

A destructor of the [List](#) class.

Destructor. Destroys the [List](#) object and all its descendants.

7.14.4 Member Function Documentation

7.14.4.1 `template<class _T> virtual void IpxCam::List<_T>::Release() [pure virtual]`

This method releases the instance of the list of the specified object.

Returns

Void.

7.14.4.2 `template<class _T> virtual size_t IpxCam::List<_T>::GetCount() [pure virtual]`

This functions gets the number of items in the specified list object.

Returns

Returns the number of items in the specified list object.

7.14.4.3 `template<class _T> virtual elem_type* IpxCam::List<_T>::GetFirst () [pure virtual]`

This method retrieves the first element in the specified list object.

Returns

Returns the first element in the specified list object.

7.14.4.4 `template<class _T> virtual elem_type* IpxCam::List<_T>::GetNext () [pure virtual]`

This method retrieves the next element in the specified list object.

Returns

Returns the next element in the specified list object.

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.15 IpxGenParam::Param Class Reference

General class for GenICam parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::Param:



Public Member Functions

- virtual [~Param](#) ()
Param class destructor. Destroys the *Param* and all its descendants.
- virtual [ParamType GetType](#) ()=0
This method returns the Parameter Node Type.
- virtual const char * [GetName](#) ()=0
This method returns the parameter node name.
- virtual const char * [GetToolTip](#) ()=0
This method returns a short description of the parameter node.
- virtual const char * [GetDescription](#) ()=0
This method returns a long description of the parameter node.
- virtual const char * [GetDisplayName](#) ()=0
This method returns the string to be used for the parameter displaying.
- virtual [Visibility GetVisibility](#) ()=0
This method returns the visibility of the node.
- virtual bool [IsValueCached](#) ()=0

- This method checks if the parameter node is cached.*
- virtual bool [IsAvailable](#) ()=0
- This method checks if parameter node is available.*
- virtual bool [IsWritable](#) ()=0
- This method checks if parameter node is writable.*
- virtual bool [IsReadable](#) ()=0
- This method checks if the parameter node is readable.*
- virtual bool [IsStreamable](#) ()=0
- This method checks if the parameter node is streamable.*
- virtual bool [IsVisible](#) ([Visibility](#) vis)=0
- This method checks if the node is visible.*
- virtual lpxCamErr [RegisterEventSink](#) ([ParamEventSink](#) *aEventSink)=0
- This method registers the event.*
- virtual lpxCamErr [UnregisterEventSink](#) ([ParamEventSink](#) *aEventSink)=0
- This method unregisters the event.*
- virtual IPX_GENAPI_NS::INode * [GetNode](#) ()=0
- This method returns the callback of the node registered.*
- virtual [Category](#) * [ToCategory](#) ()=0
- This method returns typed representation of param.*
- virtual [Boolean](#) * [ToBoolean](#) ()=0
- This method returns typed representation of param.*
- virtual [Command](#) * [ToCommand](#) ()=0
- This method returns typed representation of param.*
- virtual [EnumEntry](#) * [ToEnumEntry](#) ()=0
- This method returns typed representation of param.*
- virtual [Enum](#) * [ToEnum](#) ()=0
- This method returns typed representation of param.*
- virtual [Float](#) * [ToFloat](#) ()=0
- This method returns typed representation of param.*
- virtual [Int](#) * [ToInt](#) ()=0
- This method returns typed representation of param.*
- virtual [String](#) * [ToString](#) ()=0
- This method returns typed representation of param.*

7.15.1 Detailed Description

General class for GenICam parameter.

Class for accessing the GenICam feature node of the Camera parameters

7.15.2 Constructor & Destructor Documentation

7.15.2.1 virtual lpxGenParam::Param::~Param () [inline], [virtual]

[Param](#) class destructor. Destroys the [Param](#) and all its descendants.

[Param](#) class destructor.

7.15.3 Member Function Documentation

7.15.3.1 `virtual ParamType IpxGenParam::Param::GetType () [pure virtual]`

This method returns the Parameter Node Type.

Returns

return the parameter type.

Implemented in [IpxGenParam::String](#), [IpxGenParam::Int](#), [IpxGenParam::Float](#), [IpxGenParam::Enum](#), [IpxGenParam::EnumEntry](#), [IpxGenParam::Command](#), [IpxGenParam::Boolean](#), and [IpxGenParam::Category](#).

7.15.3.2 `virtual const char* IpxGenParam::Param::GetName () [pure virtual]`

This method returns the parameter node name.

Returns

If the method succeeds, it will return the parameter node name. Otherwise, it will return a nullptr.

7.15.3.3 `virtual const char* IpxGenParam::Param::GetToolTip () [pure virtual]`

This method returns a short description of the parameter node.

Returns

If the method succeeds, it will return a short description of the parameter node. Otherwise, it will return a nullptr.

7.15.3.4 `virtual const char* IpxGenParam::Param::GetDescription () [pure virtual]`

This method returns a long description of the parameter node.

Returns

If the method succeeds, it will return a long description of the parameter node. Otherwise, it will return a nullptr.

7.15.3.5 `virtual const char* IpxGenParam::Param::GetDisplayName () [pure virtual]`

This method returns the string to be used for the parameter displaying.

Returns

If the method succeeds, it will return the parameter display name. Otherwise, it will return a nullptr.

7.15.3.6 virtual Visibility IpxGenParam::Param::GetVisibility () [pure virtual]

This method returns the visibility of the node.

Returns

It will return the visibility setting of the parameter node. It will be either Basic, Expert, or Guru.

7.15.3.7 virtual bool IpxGenParam::Param::IsValueCached () [pure virtual]

This method checks if the parameter node is cached.

Returns

True if the value is cached. False if the value is not cached.

7.15.3.8 virtual bool IpxGenParam::Param::IsAvailable () [pure virtual]

This method checks if parameter node is available.

Returns

True if the parameter node is available. False if it is not available.

7.15.3.9 virtual bool IpxGenParam::Param::IsWritable () [pure virtual]

This method checks if parameter node is writable.

Returns

True if the parameter node is writable. False if it is not writable.

7.15.3.10 virtual bool IpxGenParam::Param::IsReadable () [pure virtual]

This method checks if the parameter node is readable.

Returns

True if the parameter node is readable. False if it is not readable.

7.15.3.11 virtual bool IpxGenParam::Param::IsStreamable () [pure virtual]

This method checks if the parameter node is streamable.

Returns

True if the parameter node is streamable. False if it is not streamable.

7.15.3.12 virtual bool IpxGenParam::Param::IsVisible (Visibility vis) [pure virtual]

This method checks if the node is visible.

Parameters

in	vis	Visibility of the parameter node
----	-----	----------------------------------

Returns

True if the parameter node is visible. False if it is not visible.

7.15.3.13 `virtual IpxCamErr IpxGenParam::Param::RegisterEventSink (ParamEventSink * aEventSink) [pure virtual]`

This method registers the event.

Parameters

in	<i>aEventSink</i>	pointer to Parameter Event Sink
----	-------------------	---------------------------------

Returns

Returns the Error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully registers event sink

7.15.3.14 `virtual IpxCamErr IpxGenParam::Param::UnregisterEventSink (ParamEventSink * aEventSink) [pure virtual]`

This method unregisters the event.

Parameters

in	<i>aEventSink</i>	pointer to Parameter Event Sink
----	-------------------	---------------------------------

Returns

Returns the Error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully unregisters event sink

7.15.3.15 `virtual IPX_GENAPI_NS::INode* IpxGenParam::Param::GetNode () [pure virtual]`

This method returns the callback of the node registered.

Returns

If the method succeeds, it will return the pointer to the node of the callback that is registered. Otherwise, it will return a value of nullptr.

7.15.3.16 `virtual Category* IpxGenParam::Param::ToCategory () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.17 `virtual Boolean* IpxGenParam::Param::ToBoolean () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.18 `virtual Command* IpxGenParam::Param::ToCommand () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.19 `virtual EnumEntry* IpxGenParam::Param::ToEnumEntry () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.20 `virtual Enum* IpxGenParam::Param::ToEnum () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.21 `virtual Float* IpxGenParam::Param::ToFloat () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.22 `virtual Int* IpxGenParam::Param::ToInt () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

7.15.3.23 `virtual String* IpxGenParam::Param::ToString () [pure virtual]`

This method returns typed representation of param.

Returns

If the method succeeds, it will return pointer to typed param. Otherwise, it will return a value of nullptr

The documentation for this class was generated from the following file:

- IpxCameraApi.h

7.16 IpxGenParam::ParamEventSink Class Reference

A Class for [ParamEventSink](#) notifications handling.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual `~ParamEventSink ()`
ParamEventSink class destructor. Destroys the ParamEventSink object and all its descendants.
- virtual void `OnParameterUpdate (Param *param)=0`
Update Parameter Node.

7.16.1 Detailed Description

A Class for [ParamEventSink](#) notifications handling.

An Event Sink class designed to receive the notifications from the GenICam parameter Node Updates

7.16.2 Member Function Documentation

7.16.2.1 `virtual void IpxGenParam::ParamEventSink::OnParameterUpdate (Param * param) [pure virtual]`

Update Parameter Node.

Parameters

in	<i>param</i>	The pointer to the Param class node
----	--------------	---

Returns

Void.

The documentation for this class was generated from the following file:

- IpxCameraApi.h

7.17 IpxCam::Stream Class Reference

The [Stream](#) class represents the data stream module in the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~Stream](#) ()
A destructor of the [Stream](#) class.
- virtual void [Release](#) ()=0
This method releases the instance of the stream object.
- virtual [IpxCam::Buffer](#) * [CreateBuffer](#) (size_t iSize, void *pPrivate, [IpxCamErr](#) *err)=0
Creates the buffer in the data stream object.
- virtual [IpxCam::Buffer](#) * [SetBuffer](#) (void *pBuffer, size_t iSize, void *pPrivate, [IpxCamErr](#) *err)=0
Sets memory buffer to create the [Buffer](#) object.
- virtual [IpxCamErr](#) [RevokeBuffer](#) ([IpxCam::Buffer](#) *buff)=0
Revokes any announced buffer.
- virtual [IpxCamErr](#) [QueueBuffer](#) ([IpxCam::Buffer](#) *buff)=0
This method queues specified buffers.
- virtual [IpxCam::Buffer](#) * [GetBuffer](#) (uint64_t iTimeout, [IpxCamErr](#) *err=nullptr)=0
This method retrieves the buffer object.
- virtual [IpxCamErr](#) [CancelBuffer](#) ()=0
Terminates the waiting operation on a previously queued [Buffer](#).
- virtual [IpxCamErr](#) [FlushBuffers](#) ([FlushOperation](#) operation)=0
This method flushes the buffers of the data stream object.
- virtual [IpxCamErr](#) [StartAcquisition](#) (uint64_t iNumFramesToAcquire=UINT64_MAX, uint32_t flags=0)=0
Starts the Acquisition Engine.
- virtual [IpxCamErr](#) [StopAcquisition](#) (uint32_t flags=0)=0
Stops the stream's acquisition engine.
- virtual [IpxCamErr](#) [AllocBufferQueue](#) (void *pPrivate, size_t iNum)=0
Allocates the [Buffer](#) Queue.

- virtual `lpxCamErr ReleaseBufferQueue ()=0`
Releases the [Buffer Queue](#).
- virtual `size_t GetBufferQueueSize ()=0`
Retrieves the [Buffer Queue](#) size.
- virtual `lpxCamErr RegisterEvent (uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0`
Registers the [EventCallback](#).
- virtual `lpxCamErr UnRegisterEvent (uint32_t eventType, lpxCam::EventCallback *eventCallback, void *pPrivate)=0`
Unregisters the [EventCallback](#).
- virtual `lpxGenParam::Array * GetParameters (lpxCamErr *err=nullptr)=0`
Returns the [GenICam](#) parameters array.
- virtual `uint64_t GetNumDelivered ()=0`
Returns the number of the delivered buffers.
- virtual `uint64_t GetNumUnderrun ()=0`
Returns the number under-run frames.
- virtual `size_t GetNumAnnounced ()=0`
Returns the number of announced buffers.
- virtual `size_t GetNumQueued ()=0`
Returns the number of queued buffers.
- virtual `size_t GetNumAwaitDelivery ()=0`
Returns the number of buffers awaiting delivery.
- virtual `size_t GetBufferSize ()=0`
Returns the buffer size.
- virtual `bool IsGrabbing ()=0`
This method returns a flag indicating if the data stream is grabbing or not.
- virtual `size_t GetMinNumBuffers ()=0`
Returns the minimum number of buffers to be announced.
- virtual `size_t GetBufferAlignment ()=0`
Returns the buffer alignment size.

7.17.1 Detailed Description

The [Stream](#) class represents the data stream module in the GenTL module hierarchy.

This data stream class provides buffer methods. This data stream class purpose is to access the buffer data acquirement from the Acquisition engine.

7.17.2 Constructor & Destructor Documentation

7.17.2.1 `virtual lpxCam::Stream::~Stream () [inline],[virtual]`

A destructor of the [Stream](#) class.

Destroys the [Stream](#) object and all its descendants.

7.17.3 Member Function Documentation

7.17.3.1 virtual void lpxCam::Stream::Release () [pure virtual]

This method releases the instance of the stream object.

Returns

void

7.17.3.2 virtual lpxCam::Buffer* lpxCam::Stream::CreateBuffer (size_t iSize, void * pPrivate, lpxCamErr * err) [pure virtual]

Creates the buffer in the data stream object.

This method allocates the memory for a buffer and announces this buffer to the data stream

Parameters

in	<i>iSize</i>	Size of the buffer
in	<i>pPrivate</i>	pointer to private data (user's data) which will be passed to the GenTL Consumer
out	<i>err</i>	returns Error code

Returns

Returns [Buffer](#) object pointer of the announced buffer

7.17.3.3 virtual lpxCam::Buffer* lpxCam::Stream::SetBuffer (void * pBuffer, size_t iSize, void * pPrivate, lpxCamErr * err) [pure virtual]

Sets memory buffer to create the [Buffer](#) object.

This method is used to set the user-allocated memory buffer to create the [Buffer](#) object and announce it to the data stream.

Parameters

in	<i>pBuffer</i>	buffer
in	<i>iSize</i>	size of Buffer
in	<i>pPrivate</i>	pointer to user's data
out	<i>err</i>	returns Error code

Returns

returns [Buffer](#) object pointer

7.17.3.4 `virtual IpxCamErr IpxCam::Stream::RevokeBuffer (IpxCam::Buffer * buff)` [pure virtual]

Revokes any announced buffer.

This method removes the specified announced [Buffer](#) from the acquisition engine's queue

Parameters

in	<i>buff</i>	Buffer object pointer
----	-------------	---------------------------------------

Returns

Returns Error code

7.17.3.5 `virtual IpxCamErr IpxCam::Stream::QueueBuffer (IpxCam::Buffer * buff)` [pure virtual]

This method queues specified buffers.

During the acquisition, this method is used to return the specified buffer to the acquisition engine's queue

Parameters

in	<i>buff</i>	Buffer object pointer
----	-------------	---------------------------------------

Returns

Returns Error code

7.17.3.6 `virtual IpxCam::Buffer* IpxCam::Stream::GetBuffer (uint64_t iTimeout, IpxCamErr * err = nullptr)` [pure virtual]

This method retrieves the buffer object.

Retrieves the next acquired buffer entry from the acquisition engine's queue and returns the acquired [Buffer](#) object

Parameters

in	<i>iTimeout</i>	timeout in ms
in	<i>err</i>	error code

Returns

Returns the pointer to the acquired [Buffer](#) object

7.17.3.7 `virtual IpxCamErr IpxCam::Stream::CancelBuffer () [pure virtual]`

Terminates the waiting operation on a previously queued [Buffer](#).

This method cancels the waiting operation on a previously queued [Buffer](#) in the acquisition engine's queue

Returns

Returns Error code

7.17.3.8 `virtual IpxCamErr IpxCam::Stream::FlushBuffers (FlushOperation operation) [pure virtual]`

This method flushes the buffers of the data stream object.

Performs the specified Flush Operation on the acquisition engine's queue. Operations type is defined in FlushOperations enum.

Parameters

in	<i>operation</i>	FlushOperation
----	------------------	----------------

Returns

Returns Error code

7.17.3.9 `virtual IpxCamErr IpxCam::Stream::StartAcquisition (uint64_t iNumFramesToAcquire = UINT64_MAX, uint32_t flags = 0) [pure virtual]`

Starts the Acquisition Engine.

This method starts the acquisition engine of the stream to acquire the image data frames to the queued buffers

Parameters

in	<i>iNumFramesToAcquire</i>	number of Frames to Acquire. Set UINT64_MAX for the infinite acquisition
in	<i>flags</i>	flags. Set to 0 by default

Returns

Returns Error code

7.17.3.10 `virtual IpxCamErr IpxCam::Stream::StopAcquisition (uint32_t flags = 0) [pure virtual]`

Stops the stream's acquisition engine.

This method stops the acquisition engine of the stream and terminates the image data frames acquisition

Parameters

in	flags	flags:
		<ul style="list-style-type: none"> • ACQ_STOP_FLAGS_DEFAULT=0, Stop the acquisition engine when the currently running tasks like filling a buffer are completed (default behavior). • ACQ_STOP_FLAGS_KILL=1, Stop the acquisition engine immediately and leave buffers currently being filled in the Input Buffer Pool.

Returns

Returns Error code

7.17.3.11 `virtual IpxCamErr IpxCam::Stream::AllocBufferQueue (void * pPrivate, size_t iNum) [pure virtual]`

Allocates the [Buffer](#) Queue.

This method allocates the buffers in the queue of the acquisition engine of the data stream object.

Parameters

in	<i>pPrivate</i>	pointer to user's data
in	<i>iNum</i>	number of the buffers to allocate

Returns

Returns Error code

7.17.3.12 `virtual IpxCamErr IpxCam::Stream::ReleaseBufferQueue () [pure virtual]`

Releases the [Buffer](#) Queue.

This method releases the buffer queue of the data stream object.

Returns

Returns Error code

7.17.3.13 `virtual size_t IpxCam::Stream::GetBufferQueueSize () [pure virtual]`

Retrieves the [Buffer](#) Queue size.

This functions returns the buffer queue size of the data stream object.

Returns

Returns the [Buffer](#) Queue size

7.17.3.14 `virtual IpxCamErr IpxCam::Stream::RegisterEvent (uint32_t eventType, IpxCam::EventCallback * eventCallback, void * pPrivate) [pure virtual]`

Registers the EventCallback.

This method registers the data [Stream](#) class method as a callback method to be called when event of the specified type occurs.

Parameters

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	event CallBack function pointer
in	<i>pPrivate</i>	pointer to the user's data

Returns

Returns Error code

7.17.3.15 `virtual IpxCamErr IpxCam::Stream::UnRegisterEvent (uint32_t eventType, IpxCam::EventCallback * eventCallback, void * pPrivate) [pure virtual]`

Unregisters the EventCallback.

This method unregisters the data [Stream](#) class callback method for the specified event type

Parameters

in	<i>eventType</i>	Event Type
in	<i>eventCallback</i>	event CallBack function pointer
in	<i>pPrivate</i>	pointer to the user's data

Returns

Returns Error code

7.17.3.16 `virtual lpxGenParam::Array* lpxCam::Stream::GetParameters (lpxCamErr * err = nullptr) [pure virtual]`

Returns the GenICam parameters array.

This method returns the pointer to [lpxGenParam::Array](#) object of the GenICam parameters array for the data stream object

Parameters

out	<i>err</i>	returns the error code
-----	------------	------------------------

Returns

Returns the data stream GenICam parameters array

7.17.3.17 `virtual uint64_t lpxCam::Stream::GetNumDelivered () [pure virtual]`

Returns the number of the delivered buffers.

This method returns the number of the delivered buffers since the start of the last acquisition

Returns

Returns the number of the delivered buffers

7.17.3.18 `virtual uint64_t lpxCam::Stream::GetNumUnderrun () [pure virtual]`

Returns the number under-run frames.

This method returns the number of the lost frames due to the acquisition queue being under-run.

Returns

Returns the number of lost frames due to queue under-run

7.17.3.19 `virtual size_t lpxCam::Stream::GetNumAnnounced () [pure virtual]`

Returns the number of announced buffers.

This method returns the number of announced buffers in the data stream acquisition queue

Returns

Returns number of announced buffers

7.17.3.20 `virtual size_t lpxCam::Stream::GetNumQueued () [pure virtual]`

Returns the number of queued buffers.

This method returns the number of queued buffers in the data stream object acquisition queue

Returns

Returns the number of buffers in the input pool and the number of buffers currently being filled

7.17.3.21 `virtual size_t lpxCam::Stream::GetNumAwaitDelivery () [pure virtual]`

Returns the number of buffers awaiting delivery.

This method returns the number of buffers awaiting the delivery from the data stream object acquisition queue to the client application

Returns

Returns the number of buffers in the output buffer queue

7.17.3.22 `virtual size_t lpxCam::Stream::GetBufferSize () [pure virtual]`

Returns the buffer size.

This method returns the buffer size of the data stream object.

Returns

Returns the buffer size

7.17.3.23 `virtual bool IpxCam::Stream::IsGrabbing () [pure virtual]`

This method returns a flag indicating if the data stream is grabbing or not.

Returns

Flag indicating the state of the acquisition engine. If true, acquisition engine has started. Otherwise, the acquisition engine is off.

7.17.3.24 `virtual size_t IpxCam::Stream::GetMinNumBuffers () [pure virtual]`

Returns the minimum number of buffers to be announced.

This method returns the minimum number of buffers to be announced in the data stream object acquisition queue to perform the grabbing

Returns

Returns the minimum number of buffers to announce

7.17.3.25 `virtual size_t IpxCam::Stream::GetBufferAlignment () [pure virtual]`

Returns the buffer alignment size.

This method returns the alignment size of the buffers in the stream object acquisition queue

Returns

Returns the alignment size in bytes of the stream buffers

The documentation for this class was generated from the following file:


- IpxCameraApi.h

7.18 IpxGenParam::String Class Reference

A class containing methods for [String](#) GenICam camera parameter.

```
#include <IpxCameraApi.h>
```

Inheritance diagram for IpxGenParam::String:



Public Member Functions

- virtual [ParamType](#) [GetType](#) ()
This method returns the node object [String](#) type.
- virtual [size_t](#) [GetMaxLength](#) ([IpxCamErr](#) *err=nullptr)=0
This method gets the Maximum Length of the string.
- virtual const char * [GetValue](#) ([size_t](#) *len=nullptr, [IpxCamErr](#) *err=nullptr)=0
This method gets the value of the string node.
- virtual [IpxCamErr](#) [SetValue](#) (const char *val)=0
This method sets the value of the string node.

7.18.1 Detailed Description

A class containing methods for [String](#) GenICam camera parameter.

A class containing methods to access the [String](#) GenICam camera parameter as zero-terminated array of characters

For example, the image below illustrates "DeviceModelName" parameter.

7.18.2 Member Function Documentation

7.18.2.1 virtual [ParamType](#) [IpxGenParam::String::GetType](#) () [\[inline\]](#),[\[virtual\]](#)

This method returns the node object [String](#) type.

Returns

The parameter type

Implements [IpxGenParam::Param](#).

7.18.2.2 virtual [size_t](#) [IpxGenParam::String::GetMaxLength](#) ([IpxCamErr](#) * *err* = nullptr) [\[pure virtual\]](#)

This method gets the Maximum Length of the string.

Parameters

out	err	returns error code:
		<ul style="list-style-type: none"> • IpxCamErr::IPX_CAM_ERR_OK - Successfully gets the maximum length value • IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR - Unable to access genicam specified node • IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR - Unable to access genicam specified node type

Returns

gets the maximum length of the string

7.18.2.3 `virtual const char* IpxGenParam::String::GetValue (size_t * len = nullptr, IpxCamErr * err = nullptr)` [pure virtual]

This method gets the value of the string node.

Parameters

out	<i>len</i>	return the length of the string
out	<i>err</i>	returns the error code: <ul style="list-style-type: none"> • <code>IpxCamErr::IPX_CAM_ERR_OK</code> - Successfully gets the string • <code>IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR</code> - Unable to access genicam specified node • <code>IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR</code> - Unable to access genicam specified node type

Returns

Returns the value

7.18.2.4 `virtual IpxCamErr IpxGenParam::String::SetValue (const char * val)` [pure virtual]

This method sets the value of the string node.

Parameters

in	<i>val</i>	Set the value of the string node
----	------------	----------------------------------

Returns

Returns the error code:

- `IpxCamErr::IPX_CAM_ERR_OK` - Successfully sets the string
- `IpxCamErr::IPX_CAM_GENICAM_ACCESS_ERROR` - Unable to access genicam specified node
- `IpxCamErr::IPX_CAM_GENICAM_TYPE_ERROR` - Unable to access genicam specified node type

The documentation for this class was generated from the following file:

- `IpxCameraApi.h`

7.19 IpxCam::System Class Reference

The [System](#) class represents an abstraction of the [System](#) module of the GenTL module hierarchy.

```
#include <IpxCameraApi.h>
```

Public Member Functions

- virtual [~System](#) ()
System class Destructor.
- virtual void [Release](#) ()=0
This method releases the instance of the system object.
- virtual [InterfaceList](#) * [GetInterfaceList](#) ([InterfaceType](#) type=[AllInterfaces](#))=0
This method returns the list of all the interfaces of the system object.
- virtual [Interface](#) * [GetInterfaceById](#) (const char *ifaceId)=0
Retrieves the interface specified by interface identifier.
- virtual const char * [GetDisplayName](#) ()=0
Retrieves the name of the GenTL Producer.
- virtual const char * [GetVersion](#) ()=0
Returns the GenTL Producer version.
- virtual [Device](#) * [CreateDeviceFromConfig](#) (const char *fileName, [IpxCamErr](#) *err=NULLPTR)=0
Creates the Device object from configuration file.
- virtual [IpxCamErr](#) [RegisterGenTLProvider](#) (const char *fileName)=0
Registers the GenTL CTI library.

7.19.1 Detailed Description

The [System](#) class represents an abstraction of the [System](#) module of the GenTL module hierarchy.

This class provides member functions to enumerate and instantiate the available interfaces reachable. It also provides a method for the configuration of the device module. This system module is the root of the GenTL Module hierarchy. [IpxCam::System](#) class has member functions to find all the interfaces, display the user readable name and producer version of the GenTL system. The [IpxCam::System](#) class can be used to obtain [IpxCam::InterfaceList](#), then get the list [IpxCam::DeviceInfo](#) objects on the [IpxCam::Interface](#), and create [IpxCam::Device](#) object, representing the camera device .

The following is an example on how to use some of the public Member Functions.

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();
IpxCam::DeviceInfo *lDeviceInfo = NULLPTR;

if (system)
{
    //Retrieve the System Name
    const char* displayname_str = system->GetDisplayName();
    std::cout << "DisplayName " << displayname_str;

    //Retrieve the Version of the System
    const char* version_str = system->GetVersion();
    std::cout << "Version " << system->GetVersion();
}
```

```

IpxCam::Interface *iface = nullptr;
IpxCam::Interface *iface2 = nullptr;
std::cout << "Interfaces Available:" << endl;

std::vector<IpxCam::Interface*> ifaceVector;

//Get the Interface List for the System
IpxCam::InterfaceList* list = system->GetInterfaceList();
for(IpxCam::List<IpxCam::Interface*>::elem_type* iface = list
->GetFirst(); iface; iface = list->GetNext())
{
    ifaceVector.push_back(iface);
    //Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->
    GetDescription() << "Id " << iface->GetId() << endl;
}

//List the number of Interfaces in the System
std::cout << "Number of Interfaces in the System: " << list->GetCount() << endl;

//Example of sending Interface By Id
iface2 = system->GetInterfaceById(ifaceVector[0]->GetId());

std::cout << "Interface Description: " << iface2->GetDescription() << endl;
lDeviceInfo = iface2->GetFirstDeviceInfo();
std::cout << "ModelName" << lDeviceInfo->GetModel() << endl;

std::cout << "Releasing system" << endl;
list->Release();
system->Release();
}

```

7.19.2 Constructor & Destructor Documentation

7.19.2.1 virtual IpxCam::System::~~System () [inline],[virtual]

[System](#) class Destructor.

Destroys the [System](#) object and all its descendants.

Here is the call graph for this function:



7.19.3 Member Function Documentation

7.19.3.1 virtual void IpxCam::System::Release () [pure virtual]

This method releases the instance of the system object.

Returns

void.

The following shows an example on how to use the **Release** method to release the system object instantiated.

```
//Get the GenTL System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Add Code Here

    //Release the GenTL System
    system->Release();
}
```

7.19.3.2 virtual InterfaceList* IpxCam::System::GetInterfaceList (InterfaceType type = AllInterfaces) [pure virtual]

This method returns the list of all the interfaces of the system object.

GetInterfaceList method lists all the available hardware interfaces with the transport layers technologies, supported by GenTL producer library

Parameters

in	type	interface type
----	------	----------------

Returns

Returns the interface list

The following is an example on how to use the **GetInterfaceList** method.

```
// Used later to get chosen interface
std::vector<IpxCam::Interface> ifaceVector;

// Get the Interface List for the System
auto list = system->GetInterfaceList();

// Get the individual Interface elements
for (auto iface = list->GetFirst(); iface; iface = list->GetNext())
{
    ifaceVector.push_back(iface);

    // Display the Interface Available
    std::cout << "[" << (ifaceVector.size() - 1) << "]" << "\t" << iface->
        GetDescription() << "Id " << iface->GetId() << endl;
}

// List has to be released
list->Release();
```

7.19.3.3 `virtual Interface* lpxCam::System::GetInterfaceByld (const char * ifaceId)` [pure virtual]

Retrieves the interface specified by interface identifier.

This method returns the interface by unique string identifier of the system object.

Parameters

in	<i>iface</i> ↔ <i>Id</i>	Interface identifier
----	-----------------------------	----------------------

Returns

Returns the [Interface](#) or nullptr if no such interface is found

For example, the const char *ifaceId interface identification name could be as shown below:

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

const char *ifaceId = "\\?\u
sb#vid_20f7&pid_30b3&mi_00#7&16f3afad&0&0000#{ff958afd-fce7-4264-994c-8fa230d5a524}";

auto iface = system->GetInterface(ifaceId);
```

This method will retrieve the available interface list of the system.

7.19.3.4 virtual const char* IpxCam::System::GetDisplayName () [pure virtual]

Retrieves the name of the GenTL Producer.

This method returns the User readable name of the GenTL Producer of the system object.

Returns

Returns the Display Name string

The following is an example on how to use the GetDisplayName method

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Retrieve the System Name
    const char* displayname_str = system->GetDisplayName();
    std::cout << "DisplayName " << displayname_str;

    // some code here

    system->Release();
}
```

7.19.3.5 virtual const char* IpxCam::System::GetVersion () [pure virtual]

Returns the GenTL Producer version.

This method returns the version of the GenTL Producer of the system object.

Returns

Returns the Version string

The following is an example on how to use the GetVersion method

```
//Get System
IpxCam::System *system = IpxCam::IpxCam_GetSystem();

if (system)
{
    //Retrieve the Version of the System
    const char* version_str = system->GetVersion();
    std::cout << "Version " << system->GetVersion();

    // some code here

    system->Release();
}
```

7.19.3.6 virtual Device* IpxCam::System::CreateDeviceFromConfig (const char * fileName, IpxCamErr * err = nullptr) [pure virtual]

Creates the [Device](#) object from configuration file.

This method creates, configures and sets up the device using the information retrieved from the specified configuration file

Parameters

in	<i>fileName</i>	Configuration file to open
out	<i>err</i>	returns the error code

Returns

Returns [Device](#) or nullptr if device cannot be instantiated

7.19.3.7 virtual IpxCamErr IpxCam::System::RegisterGenTLProvider (const char * fileName) [pure virtual]

Registers the GenTL CTI library.

This method registers the 3rd party GenTL provider CTI library in the [System](#).

Parameters

in	<i>fileName</i>	path to GenTL CTI file to add
----	-----------------	-------------------------------

Returns

Returns the error code

The documentation for this class was generated from the following file:

- IpxCameraApi.h

Index

- ~Array
 - IpxGenParam::Array, [29](#)
- ~Buffer
 - IpxCam::Buffer, [43](#)
- ~Device
 - IpxCam::Device, [53](#)
- ~DeviceInfo
 - IpxCam::DeviceInfo, [59](#)
- ~IpxGenParamTreeView
 - IpxGui::IpxGenParamTreeView, [74](#)
- ~Interface
 - IpxCam::Interface, [83](#)
- ~List
 - IpxCam::List, [90](#)
- ~Param
 - IpxGenParam::Param, [93](#)
- ~Stream
 - IpxCam::Stream, [100](#)
- ~System
 - IpxCam::System, [112](#)
- AllInterfaces
 - IpxCam, [13](#)
- AllocBufferQueue
 - IpxCam::Stream, [104](#)
- Beginner
 - IpxGui, [17](#)
- BigEndian
 - IpxCam::Device, [52](#)
- CameraLink
 - IpxCam, [13](#)
- CancelBuffer
 - IpxCam::Stream, [103](#)
- clearParams
 - IpxGui::IpxGenParamTreeView, [76](#)
- CoaxPress
 - IpxCam, [13](#)
- Control
 - IpxCam, [13](#)
- CreateBuffer
 - IpxCam::Stream, [101](#)
- CreateDeviceFromConfig
 - IpxCam::Interface, [87](#)
 - IpxCam::System, [116](#)
- CreateGenParamTreeViewForArrayA
 - IpxGui, [18](#)
- CreateGenParamTreeViewForArrayW
 - IpxGui, [18](#)
- CreateGenParamTreeViewForNodemapA
 - IpxGui, [19](#)
- CreateGenParamTreeViewForNodemapW
 - IpxGui, [19](#)
- DestroyGenParamTreeView
 - IpxGui, [20](#)
- DeviceAccess
 - IpxCam, [13](#)
- DeviceInfoList
 - IpxCam, [12](#)
- DeviceList
 - IpxCam, [12](#)
- elem_type
 - IpxCam::List, [90](#)
- Endianness
 - IpxCam::Device, [52](#)
- EventCallback
 - IpxCam, [12](#)
- EventCallback2
 - IpxCam, [12](#)
- Exclusive
 - IpxCam, [13](#)
- Execute
 - IpxGenParam::Command, [50](#)
- ExecuteCommand
 - IpxGenParam::Array, [38](#)
- Expert
 - IpxGui, [17](#)
- FlashPageRead
 - IpxCam::Device, [52](#)
- FlashPageWrite
 - IpxCam::Device, [52](#)
- FlashSectorErase
 - IpxCam::Device, [52](#)
- Flush_AllDiscard
 - IpxCam, [13](#)
- Flush_AllToInput
 - IpxCam, [13](#)
- Flush_OutputDiscard

- IpxCam, [13](#)
- Flush_UnqueuedToInput
 - IpxCam, [13](#)
- FlushBuffers
 - IpxCam::Stream, [103](#)
- FlushOperation
 - IpxCam, [13](#)
- ForceIP
 - IpxCam::DeviceInfo, [62](#)
- GetAccessStatus
 - IpxCam::DeviceInfo, [60](#)
- GetBoolean
 - IpxGenParam::Array, [29](#)
- GetBooleanValue
 - IpxGenParam::Array, [33](#)
- GetBuffer
 - IpxCam::Stream, [102](#)
- GetBufferAlignment
 - IpxCam::Stream, [108](#)
- GetBufferPtr
 - IpxCam::Buffer, [43](#)
- GetBufferQueueSize
 - IpxCam::Stream, [105](#)
- GetBufferSize
 - IpxCam::Buffer, [44](#)
 - IpxCam::Stream, [107](#)
- GetCameraParameters
 - IpxCam::Device, [56](#)
- GetCommand
 - IpxGenParam::Array, [30](#)
- GetCount
 - IpxCam::List, [90](#)
 - IpxGenParam::Array, [33](#)
 - IpxGenParam::Category, [48](#)
- GetDeliveredHeight
 - IpxCam::Buffer, [47](#)
- GetDescription
 - IpxCam::Interface, [85](#)
 - IpxGenParam::Param, [94](#)
- GetDeviceInfoById
 - IpxCam::Interface, [84](#)
- GetDeviceInfoList
 - IpxCam::Interface, [83](#)
- GetDisplayName
 - IpxCam::DeviceInfo, [59](#)
 - IpxCam::System, [115](#)
 - IpxGenParam::Param, [94](#)
- GetEndianness
 - IpxCam::Device, [57](#)
- GetEnum
 - IpxGenParam::Array, [30](#)
- GetEnumEntriesCount
 - IpxGenParam::Enum, [64](#)

- GetEnumEntryByIndex
 - IpxGenParam::Enum, [65](#)
- GetEnumEntryByName
 - IpxGenParam::Enum, [65](#)
- GetEnumEntryByValue
 - IpxGenParam::Enum, [65](#)
- GetEnumValue
 - IpxGenParam::Array, [35](#)
- GetEnumValueStr
 - IpxGenParam::Array, [35](#)
- GetFirst
 - IpxCam::List, [90](#)
- GetFirstDeviceInfo
 - IpxCam::Interface, [84](#)
- GetFloat
 - IpxGenParam::Array, [30](#)
- GetFloatValue
 - IpxGenParam::Array, [36](#)
- GetFrameID
 - IpxCam::Buffer, [45](#)
- GetHeight
 - IpxCam::Buffer, [45](#)
- GetIPAddress
 - IpxCam::DeviceInfo, [61](#)
- GetIPGateway
 - IpxCam::DeviceInfo, [61](#)
- GetIPMask
 - IpxCam::DeviceInfo, [61](#)
- GetID
 - IpxCam::DeviceInfo, [59](#)
- GetId
 - IpxCam::Interface, [85](#)
- GetImage
 - IpxCam::Buffer, [43](#)
- GetImageOffset
 - IpxCam::Buffer, [44](#)
- GetIncrement
 - IpxGenParam::Int, [81](#)
- GetInfo
 - IpxCam::Device, [53](#)
- GetInt
 - IpxGenParam::Array, [31](#)
- GetIntegerValue
 - IpxGenParam::Array, [37](#)
- GetInterface
 - IpxCam::DeviceInfo, [59](#)
- GetInterfaceById
 - IpxCam::System, [113](#)
- GetInterfaceList
 - IpxCam::System, [113](#)
- GetIP
 - IpxCam::DeviceInfo, [62](#)
- GetMax
 - IpxGenParam::Float, [72](#)

- [IpxGenParam::Int, 81](#)
- [GetMaxLength](#)
 - [IpxGenParam::String, 109](#)
- [GetMin](#)
 - [IpxGenParam::Float, 71](#)
 - [IpxGenParam::Int, 81](#)
- [GetMinNumBuffers](#)
 - [IpxCam::Stream, 108](#)
- [GetModel](#)
 - [IpxCam::DeviceInfo, 59](#)
- [GetName](#)
 - [IpxGenParam::Param, 94](#)
- [GetNext](#)
 - [IpxCam::List, 91](#)
- [GetNode](#)
 - [IpxGenParam::Param, 96](#)
- [GetNodeMap](#)
 - [IpxGenParam::Array, 32](#)
- [GetNumAnnounced](#)
 - [IpxCam::Stream, 106](#)
- [GetNumAwaitDelivery](#)
 - [IpxCam::Stream, 107](#)
- [GetNumDelivered](#)
 - [IpxCam::Stream, 106](#)
- [GetNumQueued](#)
 - [IpxCam::Stream, 107](#)
- [GetNumStreams](#)
 - [IpxCam::Device, 53](#)
- [GetNumUnderrun](#)
 - [IpxCam::Stream, 106](#)
- [GetParam](#)
 - [IpxGenParam::Array, 29](#)
- [GetParamByIndex](#)
 - [IpxGenParam::Array, 33](#)
 - [IpxGenParam::Category, 48](#)
- [GetParameters](#)
 - [IpxCam::Interface, 87](#)
 - [IpxCam::Stream, 106](#)
- [GetPixelFormat](#)
 - [IpxCam::Buffer, 44](#)
- [getPollingTime](#)
 - [IpxGui::IpxGenParamTreeView, 78](#)
- [GetRootCategory](#)
 - [IpxGenParam::Array, 32](#)
- [GetSerialNumber](#)
 - [IpxCam::DeviceInfo, 60](#)
- [GetStreamById](#)
 - [IpxCam::Device, 53](#)
- [GetStreamByIndex](#)
 - [IpxCam::Device, 53](#)
- [GetString](#)
 - [IpxGenParam::Array, 31](#)
- [GetStringValue](#)
 - [IpxGenParam::Array, 38](#)
- [GetTimestamp](#)
 - [IpxCam::Buffer, 44](#)
- [GetToolTip](#)
 - [IpxGenParam::Param, 94](#)
- [GetTransportParameters](#)
 - [IpxCam::Device, 56](#)
- [GetType](#)
 - [IpxCam::Interface, 85](#)
 - [IpxGenParam::Boolean, 41](#)
 - [IpxGenParam::Category, 48](#)
 - [IpxGenParam::Command, 50](#)
 - [IpxGenParam::Enum, 64](#)
 - [IpxGenParam::EnumEntry, 68](#)
 - [IpxGenParam::Float, 70](#)
 - [IpxGenParam::Int, 80](#)
 - [IpxGenParam::Param, 94](#)
 - [IpxGenParam::String, 109](#)
- [GetUSB3HostInfo](#)
 - [IpxCam::DeviceInfo, 60](#)
- [GetUnit](#)
 - [IpxGenParam::Float, 72](#)
- [GetUserDefinedName](#)
 - [IpxCam::DeviceInfo, 60](#)
- [GetUserPtr](#)
 - [IpxCam::Buffer, 44](#)
- [GetValue](#)
 - [IpxGenParam::Boolean, 41](#)
 - [IpxGenParam::Enum, 66](#)
 - [IpxGenParam::EnumEntry, 68](#)
 - [IpxGenParam::Float, 71](#)
 - [IpxGenParam::Int, 80](#)
 - [IpxGenParam::String, 110](#)
- [GetValueStr](#)
 - [IpxGenParam::Enum, 66](#)
 - [IpxGenParam::EnumEntry, 69](#)
- [GetVendor](#)
 - [IpxCam::DeviceInfo, 59](#)
- [GetVersion](#)
 - [IpxCam::DeviceInfo, 60](#)
 - [IpxCam::Interface, 86](#)
 - [IpxCam::System, 115](#)
- [GetVisibility](#)
 - [IpxGenParam::Param, 94](#)
- [GetWidth](#)
 - [IpxCam::Buffer, 45](#)
- [GetXOffset](#)
 - [IpxCam::Buffer, 46](#)
- [GetXPadding](#)
 - [IpxCam::Buffer, 46](#)
- [GetYOffset](#)
 - [IpxCam::Buffer, 46](#)
- [GetYPadding](#)
 - [IpxCam::Buffer, 46](#)
- [GigEVision](#)

- lpxCam, 13
- Guru
 - lpxGui, 17
- HdSdi
 - lpxCam, 13
- InterfaceList
 - lpxCam, 12
- InterfaceType
 - lpxCam, 13
- lpxCam, 11
 - AllInterfaces, 13
 - CameraLink, 13
 - CoaxPress, 13
 - Control, 13
 - DeviceAccess, 13
 - DeviceInfoList, 12
 - DeviceList, 12
 - EventCallback, 12
 - EventCallback2, 12
 - Exclusive, 13
 - Flush_AllDiscard, 13
 - Flush_AllToInput, 13
 - Flush_OutputDiscard, 13
 - Flush_UnqueuedToInput, 13
 - FlushOperation, 13
 - GigEVision, 13
 - HdSdi, 13
 - InterfaceList, 12
 - InterfaceType, 13
 - lpxCam_GetSystem, 14
 - ReadOnly, 13
 - USB3Vision, 13
- lpxCam::Buffer, 42
 - ~Buffer, 43
 - GetBufferPtr, 43
 - GetBufferSize, 44
 - GetDeliveredHeight, 47
 - GetFrameID, 45
 - GetHeight, 45
 - GetImage, 43
 - GetImageOffset, 44
 - GetPixelFormat, 44
 - GetTimestamp, 44
 - GetUserPtr, 44
 - GetWidth, 45
 - GetXOffset, 46
 - GetXPadding, 46
 - GetYOffset, 46
 - GetYPadding, 46
 - IsIncomplete, 45
 - IsKacFrameB, 47
- lpxCam::Device, 51
 - ~Device, 53
- BigEndian, 52
- Endianness, 52
- FlashPageRead, 52
- FlashPageWrite, 52
- FlashSectorErase, 52
- GetCameraParameters, 56
- GetEndianness, 57
- GetInfo, 53
- GetNumStreams, 53
- GetStreamById, 53
- GetStreamByIndex, 53
- GetTransportParameters, 56
- LittleEndian, 52
- LoadConfiguration, 57
- ReadMem, 54
- RegisterEvent, 55
- RegisterEvent2, 54
- SaveConfiguration, 56
- UnRegisterEvent, 56
- UnRegisterEvent2, 55
- UploadEventType, 52
- WriteMem, 54
- lpxCam::DeviceInfo, 57
 - ~DeviceInfo, 59
 - ForceIP, 62
 - GetAccessStatus, 60
 - GetDisplayName, 59
 - GetIPAddress, 61
 - GetIPGateway, 61
 - GetIPMask, 61
 - GetID, 59
 - GetInterface, 59
 - GetIP, 62
 - GetModel, 59
 - GetSerialNumber, 60
 - GetUSB3HostInfo, 60
 - GetUserDefinedName, 60
 - GetVendor, 59
 - GetVersion, 60
- lpxCam::Interface, 82
 - ~Interface, 83
 - CreateDeviceFromConfig, 87
 - GetDescription, 85
 - GetDeviceInfoById, 84
 - GetDeviceInfoList, 83
 - GetFirstDeviceInfo, 84
 - GetId, 85
 - GetParameters, 87
 - GetType, 85
 - GetVersion, 86
 - ReEnumerateDevices, 85
 - RegisterEvent, 86
 - RegisterEvent2, 86
 - UnRegisterEvent, 87

- UnRegisterEvent2, 86
- IpxCam::List
 - ~List, 90
 - elem_type, 90
 - GetCount, 90
 - GetFirst, 90
 - GetNext, 91
 - Release, 90
- IpxCam::List<_T>, 88
- IpxCam::Stream, 99
 - ~Stream, 100
 - AllocBufferQueue, 104
 - CancelBuffer, 103
 - CreateBuffer, 101
 - FlushBuffers, 103
 - GetBuffer, 102
 - GetBufferAlignment, 108
 - GetBufferQueueSize, 105
 - GetBufferSize, 107
 - GetMinNumBuffers, 108
 - GetNumAnnounced, 106
 - GetNumAwaitDelivery, 107
 - GetNumDelivered, 106
 - GetNumQueued, 107
 - GetNumUnderrun, 106
 - GetParameters, 106
 - IsGrabbing, 107
 - QueueBuffer, 102
 - RegisterEvent, 105
 - Release, 101
 - ReleaseBufferQueue, 104
 - RevokeBuffer, 102
 - SetBuffer, 101
 - StartAcquisition, 103
 - StopAcquisition, 104
 - UnRegisterEvent, 105
- IpxCam::System, 111
 - ~System, 112
 - CreateDeviceFromConfig, 116
 - GetDisplayName, 115
 - GetInterfaceById, 113
 - GetInterfaceList, 113
 - GetVersion, 115
 - RegisterGenTLProvider, 116
 - Release, 112
- IpxCam_GetSystem
 - IpxCam, 14
- IpxGenParam, 14
 - Namespace, 15
 - NamespaceCustom, 15
 - NamespaceStandard, 15
 - NamespaceUndefined, 15
 - ParamBoolean, 15
 - ParamCategory, 15
 - ParamCommand, 15
 - ParamEnum, 15
 - ParamEnumEntry, 15
 - ParamFloat, 15
 - ParamInt, 15
 - ParamString, 15
 - ParamType, 15
 - ParamUnknown, 15
 - VisBeginner, 16
 - VisExpert, 16
 - VisGuru, 16
 - VisInvisible, 16
 - VisUndefined, 16
 - Visibility, 15
- IpxGenParam::Array, 27
 - ~Array, 29
 - ExecuteCommand, 38
 - GetBoolean, 29
 - GetBooleanValue, 33
 - GetCommand, 30
 - GetCount, 33
 - GetEnum, 30
 - GetEnumValue, 35
 - GetEnumValueStr, 35
 - GetFloat, 30
 - GetFloatValue, 36
 - GetInt, 31
 - GetIntegerValue, 37
 - GetNodeMap, 32
 - GetParam, 29
 - GetParamByIndex, 33
 - GetRootCategory, 32
 - GetString, 31
 - GetStringValue, 38
 - IsCommandDone, 39
 - Poll, 39
 - SetBooleanValue, 33
 - SetEnumValue, 34
 - SetEnumValueStr, 34
 - SetFloatValue, 36
 - SetIntegerValue, 37
 - SetStringValue, 37
- IpxGenParam::Boolean, 40
 - GetType, 41
 - GetValue, 41
 - SetValue, 41
- IpxGenParam::Category, 47
 - GetCount, 48
 - GetParamByIndex, 48
 - GetType, 48
- IpxGenParam::Command, 49
 - Execute, 50
 - GetType, 50
 - IsDone, 50

- IpxGenParam::Enum, 63
 - GetEnumEntriesCount, 64
 - GetEnumEntryByIndex, 65
 - GetEnumEntryByName, 65
 - GetEnumEntryByValue, 65
 - GetType, 64
 - GetValue, 66
 - GetValueStr, 66
 - SetValue, 67
 - SetValueStr, 67
- IpxGenParam::EnumEntry, 67
 - GetType, 68
 - GetValue, 68
 - GetValueStr, 69
- IpxGenParam::Float, 69
 - GetMax, 72
 - GetMin, 71
 - GetType, 70
 - GetUnit, 72
 - GetValue, 71
 - SetValue, 70
- IpxGenParam::Int, 79
 - GetIncrement, 81
 - GetMax, 81
 - GetMin, 81
 - GetType, 80
 - GetValue, 80
 - SetValue, 80
- IpxGenParam::Param, 91
 - ~Param, 93
 - GetDescription, 94
 - GetDisplayName, 94
 - GetName, 94
 - GetNode, 96
 - GetToolTip, 94
 - GetType, 94
 - GetVisibility, 94
 - IsAvailable, 95
 - IsReadable, 95
 - IsStreamable, 95
 - IsValueCached, 95
 - IsVisible, 95
 - IsWritable, 95
 - RegisterEventSink, 96
 - ToBoolean, 97
 - ToCategory, 96
 - ToCommand, 97
 - ToEnum, 97
 - ToEnumEntry, 97
 - ToFloat, 97
 - ToInt, 98
 - ToString, 98
 - UnregisterEventSink, 96
- IpxGenParam::ParamEventSink, 98
 - OnParameterUpdate, 98
- IpxGenParam::String, 108
 - GetMaxLength, 109
 - GetType, 109
 - GetValue, 110
 - SetValue, 110
- IpxGui, 16
 - Beginner, 17
 - CreateGenParamTreeViewForArrayA, 18
 - CreateGenParamTreeViewForArrayW, 18
 - CreateGenParamTreeViewForNodemapA, 19
 - CreateGenParamTreeViewForNodemapW, 19
 - DestroyGenParamTreeView, 20
 - Expert, 17
 - Guru, 17
 - SelectCameraA, 21
 - SelectCameraW, 21
 - ShowCamConfigDialog, 22
 - ShowColorDialog, 25
 - ShowFrameABDialog, 23
 - ShowOutputDialog, 25
 - ShowPulseDialog, 24
 - ShowStrobeDialog, 24
 - ShowTriggerDialog, 23
 - Visibility, 17
- IpxGui::IpxGenParamTreeView, 73
 - ~IpxGenParamTreeView, 74
 - clearParams, 76
 - getPollingTime, 78
 - loadState, 78
 - saveState, 77
 - setParams, 75, 76
 - setPollingTime, 78
 - setVisibility, 77
 - visibility, 77
- IsAvailable
 - IpxGenParam::Param, 95
- IsCommandDone
 - IpxGenParam::Array, 39
- IsDone
 - IpxGenParam::Command, 50
- IsGrabbing
 - IpxCam::Stream, 107
- IsIncomplete
 - IpxCam::Buffer, 45
- IsKacFrameB
 - IpxCam::Buffer, 47
- IsReadable
 - IpxGenParam::Param, 95
- IsStreamable
 - IpxGenParam::Param, 95
- IsValueCached
 - IpxGenParam::Param, 95
- IsVisible

- IpxGenParam::Param, [95](#)
- IsWritable
 - IpxGenParam::Param, [95](#)
- LittleEndian
 - IpxCam::Device, [52](#)
- LoadConfiguration
 - IpxCam::Device, [57](#)
- loadState
 - IpxGui::IpxGenParamTreeView, [78](#)
- Namespace
 - IpxGenParam, [15](#)
- NamespaceCustom
 - IpxGenParam, [15](#)
- NamespaceStandard
 - IpxGenParam, [15](#)
- NamespaceUndefined
 - IpxGenParam, [15](#)
- OnParameterUpdate
 - IpxGenParam::ParamEventSink, [98](#)
- ParamBoolean
 - IpxGenParam, [15](#)
- ParamCategory
 - IpxGenParam, [15](#)
- ParamCommand
 - IpxGenParam, [15](#)
- ParamEnum
 - IpxGenParam, [15](#)
- ParamEnumEntry
 - IpxGenParam, [15](#)
- ParamFloat
 - IpxGenParam, [15](#)
- ParamInt
 - IpxGenParam, [15](#)
- ParamString
 - IpxGenParam, [15](#)
- ParamType
 - IpxGenParam, [15](#)
- ParamUnknown
 - IpxGenParam, [15](#)
- Poll
 - IpxGenParam::Array, [39](#)
- QueueBuffer
 - IpxCam::Stream, [102](#)
- ReEnumerateDevices
 - IpxCam::Interface, [85](#)
- ReadMem
 - IpxCam::Device, [54](#)
- ReadOnly
 - IpxCam, [13](#)
- RegisterEvent
 - IpxCam::Device, [55](#)
 - IpxCam::Interface, [86](#)
 - IpxCam::Stream, [105](#)
- RegisterEvent2
 - IpxCam::Device, [54](#)
 - IpxCam::Interface, [86](#)
- RegisterEventSink
 - IpxGenParam::Param, [96](#)
- RegisterGenTLProvider
 - IpxCam::System, [116](#)
- Release
 - IpxCam::List, [90](#)
 - IpxCam::Stream, [101](#)
 - IpxCam::System, [112](#)
- ReleaseBufferQueue
 - IpxCam::Stream, [104](#)
- RevokeBuffer
 - IpxCam::Stream, [102](#)
- SaveConfiguration
 - IpxCam::Device, [56](#)
- saveState
 - IpxGui::IpxGenParamTreeView, [77](#)
- SelectCameraA
 - IpxGui, [21](#)
- SelectCameraW
 - IpxGui, [21](#)
- SetBooleanValue
 - IpxGenParam::Array, [33](#)
- SetBuffer
 - IpxCam::Stream, [101](#)
- SetEnumValue
 - IpxGenParam::Array, [34](#)
- SetEnumValueStr
 - IpxGenParam::Array, [34](#)
- SetFloatValue
 - IpxGenParam::Array, [36](#)
- SetIntegerValue
 - IpxGenParam::Array, [37](#)
- setParams
 - IpxGui::IpxGenParamTreeView, [75](#), [76](#)
- setPollingTime
 - IpxGui::IpxGenParamTreeView, [78](#)
- SetStringValue
 - IpxGenParam::Array, [37](#)
- SetValue
 - IpxGenParam::Boolean, [41](#)
 - IpxGenParam::Enum, [67](#)
 - IpxGenParam::Float, [70](#)
 - IpxGenParam::Int, [80](#)
 - IpxGenParam::String, [110](#)
- SetValueStr
 - IpxGenParam::Enum, [67](#)

- setVisibility
 - IpxGui::IpxGenParamTreeView, [77](#)
- ShowCamConfigDialog
 - IpxGui, [22](#)
- ShowColorDialog
 - IpxGui, [25](#)
- ShowFrameABDialog
 - IpxGui, [23](#)
- ShowOutputDialog
 - IpxGui, [25](#)
- ShowPulseDialog
 - IpxGui, [24](#)
- ShowStrobeDialog
 - IpxGui, [24](#)
- ShowTriggerDialog
 - IpxGui, [23](#)
- StartAcquisition
 - IpxCam::Stream, [103](#)
- StopAcquisition
 - IpxCam::Stream, [104](#)
- ToBoolean
 - IpxGenParam::Param, [97](#)
- ToCategory
 - IpxGenParam::Param, [96](#)
- ToCommand
 - IpxGenParam::Param, [97](#)
- ToEnum
 - IpxGenParam::Param, [97](#)
- ToEnumEntry
 - IpxGenParam::Param, [97](#)
- ToFloat
 - IpxGenParam::Param, [97](#)
- ToInt
 - IpxGenParam::Param, [98](#)
- ToString
 - IpxGenParam::Param, [98](#)
- USB3Vision
 - IpxCam, [13](#)
- UnRegisterEvent
 - IpxCam::Device, [56](#)
 - IpxCam::Interface, [87](#)
 - IpxCam::Stream, [105](#)
- UnRegisterEvent2
 - IpxCam::Device, [55](#)
 - IpxCam::Interface, [86](#)
- UnregisterEventSink
 - IpxGenParam::Param, [96](#)
- UploadEventType
 - IpxCam::Device, [52](#)
- VisBeginner
 - IpxGenParam, [16](#)
- VisExpert
 - IpxGenParam, [16](#)
- VisGuru
 - IpxGenParam, [16](#)
- VisInvisible
 - IpxGenParam, [16](#)
- VisUndefined
 - IpxGenParam, [16](#)
- Visibility
 - IpxGenParam, [15](#)
 - IpxGui, [17](#)
- visibility
 - IpxGui::IpxGenParamTreeView, [77](#)
- WriteMem
 - IpxCam::Device, [54](#)